



Navicat

Version 17

User Guide



Table of Contents

Chapter 1 - Introduction	12
About Navicat	12
Installation	15
Registration	15
Migration / Upgrade	16
End-User License Agreement	17
Chapter 2 - User Interface	24
Main Window	24
Navigation Pane	25
Object Pane	25
Information Pane	27
Chapter 3 - Collaboration	29
About Collaboration	29
Manage Cloud	29
Navicat Cloud	29
On-Prem Server	31
Push Synchronization	33
Cache and Local Copies	34
Projects	34
Work With Projects	34
Manage Members	35
Chapter 4 - Connection	37
About Connection	37
General Settings	39
RDBMS	39
MongoDB	41
Redis	42
Advanced Settings	43
Databases Settings	46
SSL Settings	47
SSH Settings	49
HTTP Settings	50
Compatibility Settings	51
Connect with Different Profiles	51
Manage Connections	52
Chapter 5 - Server Objects	54
About Server Objects	54
MySQL / MariaDB	54
Databases	54
Tables	54

Views	55
Procedures / Functions	56
Tablespaces	57
Events	57
Other Objects	57
Maintain Objects	57
Oracle	58
Schemas	58
Tables	58
Views	59
Materialized Views	59
Procedures / Functions	60
Packages	61
Recycle Bin	62
Other Objects	63
Maintain Objects	63
PostgreSQL	65
Databases & Schemas	65
Tables	66
Views	67
Materialized Views	67
Procedures / Functions	68
Types	69
Foreign Servers	69
Other Objects	69
Maintain Objects	70
Manage Extensions	70
SQL Server	71
Databases & Schemas	71
Tables	71
Views	72
Procedures / Functions	73
Other Objects	74
Maintain Objects	74
SQLite	75
Databases	75
Tables	75
Views	76
Other Objects	76
Maintain Objects	76
MongoDB	77
Databases	77

Collections	77
Views	78
Functions	78
Indexes	79
MapReduce	79
GridFS	79
Maintain Objects	80
Redis	81
Databases	81
Data	81
Chapter 6 - Data Viewer	82
About Data Viewer	82
RDBMS	82
RDBMS Data Viewer	82
Use Navigation Bar	82
Edit Records	83
Sort / Find / Replace Records	88
Filter Records	89
Manipulate Raw Data	90
Format Data View	90
View Field Information	91
MongoDB	92
MongoDB Data Viewer	92
Use Navigation Bar	92
Grid View	93
Tree View	96
JSON View	98
Sort / Find / Replace Documents	98
Filter Documents	99
Format Data View	100
Redis	101
Redis Data Viewer	101
Use Navigation Bar	101
Edit Keys	102
Sort Keys	103
Search Keys	103
Cell Editors	103
Filter & Sort Pane	104
Chapter 7 - Data Profiling (Available only in Navicat Premium, Enterprise and Standard Edition)	107
About Data Profiling	107
Start Data Profiling	107
View Profiling Results	107

Chapter 8 - Query	111
About Query	111
RDBMS	112
Query Editor	112
Query Builder (Available only in Navicat Premium, Enterprise and Standard Edition)	116
Query Parameters	121
Debug Oracle Query (Available only in Navicat Premium, Enterprise and Standard Edition)	121
Query Results	121
Query Explain	123
MongoDB	124
Query Editor	124
Find Builder (Available only in Navicat Premium, Enterprise and Standard Edition)	127
Aggregate Builder (Available only in Navicat Premium, Enterprise and Standard Edition)	128
Query Results	128
Query Explain	129
Redis	129
Query Editor	129
Query Results	132
Code Snippets	134
Chapter 9 - Model (Available only in Navicat Premium and Enterprise Edition)	136
About Model	136
Workspace	137
Model	138
About Model	138
Create Model	138
Create Table	139
Create View	139
Create Function / Procedure	140
Create Collection	140
Create Predefined Object	141
Create Entity	141
Diagram	141
About Diagram	141
Create Diagram	143
Add Model Objects	143
Add Tables	144
Add Collections	145
Add Foreign Keys	147
Add Views	148
Add Functions / Procedures	149
Add Entities	150
Add Labels	152

Add Notes	153
Add Images	154
Add Shapes	155
Add Layers	157
Work with Diagram Canvas	158
Apply Auto Layout	159
Preview Diagram	159
Print & Export Diagram	160
Data Dictionary	160
About Data Dictionary	160
Create Data Dictionary	160
Reverse Engineering	161
About Reverse Engineering	161
Synchronize Database to Model	161
Reverse Database to Model	163
Forward Engineering	163
About Forward Engineering	163
Synchronize Model to Database	164
Export Model to SQL/Script File	166
Compare Model Workspace	167
Model Conversion	168
Model Hints and Tips	169
Chapter 10 - Debugger (Available only in Navicat Premium, Enterprise and Standard Edition)	172
About Debugger	172
Oracle PL/SQL Debugger	172
PostgreSQL PL/pgSQL Debugger	173
Chapter 11 - Pub/Sub (Available only in Navicat Premium, Enterprise and Standard Edition)	175
About Pub/Sub	175
Pub/Sub Window	175
Subscribe Channels	176
Channel Colorings	177
Chapter 12 - Aggregation Pipeline (Available only in Navicat Premium, Enterprise and Standard Edition)	178
About Aggregation Pipeline	178
Pipeline Builder	178
Pipeline Results	180
Pipeline Explain	180
Chapter 13 - Data Migration Tools	181
About Data Migration Tools	181
Import Wizard	181
About Import Wizard	181
Choose File Format	181
Choose Files	181

Choose Record Format / File Options	182
Choose Format Options	183
Map Tables / Collections	184
Map Fields	184
Choose Import Mode	185
Save and Start Import	186
Export Wizard	186
About Export Wizard	186
Choose File Format	186
Choose Saving Path	187
Choose Table / Collection Fields	187
Choose Additional Options	187
Save and Start Export	189
Data Transfer (Available only in Navicat Premium, Enterprise and Standard Edition)	190
About Data Transfer	190
Choose Connections & Advanced Options (Step 1)	190
Choose Objects & Transfer Mode (Step 2)	194
Confirm & Start Data Transfer (Step 3)	195
Data Synchronization (Available only in Navicat Premium, Enterprise and Standard Edition)	195
About Data Synchronization	195
Choose Connections & Comparing Options (Step 1)	196
Choose Table / Collection Mapping (Step 2)	196
View Data Comparison Results (Step 3)	197
Edit & Execute Selected Scripts (Step 4)	197
Structure Synchronization (Available only in Navicat Premium, Enterprise and Standard Edition)	198
About Structure Synchronization	198
Choose Connections & Comparing Options (Step 1)	198
View Structure Comparison Results (Step 2)	201
Edit & Execute Selected Scripts (Step 3)	201
Dump & Execute SQL / Script File	202
Execute Command File	203
MongoImport & MongoExport	203
About MongoImport & MongoExport	203
MongoImport	203
MongoExport	204
Chapter 14 - Data Generation (Available only in Navicat Premium, Enterprise and Standard Edition)	205
About Data Generation	205
Choose Target Connection (Step 1)	205
Choose Objects & Column Properties (Step 2)	206
Use Generator (Step 2.1)	207
Number Generator	207
Date / Time / DateTime Generator	207

Sequence Generator	208
Enum Generator	209
Text Generator	209
Image/Binary Generator	210
Foreign Key Generator	210
UUID Generator	211
Regular Expression Generator	212
Name Generator	213
Gender Generator	214
Title Generator	214
Marital Status Generator	215
Phone Number Generator	215
Email Generator	216
Job Title Generator	216
Social Network ID Generator	217
Payment Method Generator	217
Credit Card Type Generator	217
Credit Card Number Generator	218
Credit Card Date Generator	218
Company Name Generator	219
Department Generator	219
Industry Generator	220
Address Generator	220
City Generator	221
Region Generator	221
Product Name Generator	222
Product Category Generator	222
Color Generator	223
Size Generator	223
Weight Unit Generator	223
Barcode Generator	224
SKU Generator	225
IP Address Generator	225
MAC Address Generator	226
File Path Generator	226
File Name Generator	227
File Extension Generator	227
URL Generator	228
Hostname Generator	229
Preview Data & Start Generation (Step 3)	229
Chapter 15 - Data Dictionary (Available only in Navicat Premium, Enterprise and Standard Edition)	230
About Data Dictionary	230

Choose Databases (Step 1)	230
Choose Objects & Change Order (Step 2)	230
Choose Template (Step 3)	230
Adjust Layout Settings (Step 4)	230
Set File Path & Start Generation (Step 5)	231
Chapter 16 - BI (Available only in Navicat Premium and Enterprise Edition)	233
About BI	233
Workspace	234
Data Source	235
About Data Source	235
Create Data Source	236
Modify Data Source Connections	238
Filter / Sort / Project Data	239
Add Custom Fields	241
Chart	243
About Chart	243
Build Chart	244
Filter / Sort Data	246
Apply Aggregate Function	247
Add Range	248
Set Value Operation	248
Present Chart	249
Chart Types	249
About Chart Types	249
Bar Chart	250
Line / Area Chart	253
Bar and Line Chart	256
Waterfall Chart	260
Tornado Chart	262
Pie / Donut Chart	264
Scatter Chart	266
Heatmap	269
Treemap	270
Value	272
Trend	273
KPI	274
Gauge	275
Table	277
Pivot Table	278
Control	280
DateTime Formats	281
Dashboard	282

About Dashboard	282
Build Dashboard	283
Add Pages	283
Add Charts	284
Add Text Labels	284
Add Images	285
Add Shapes	285
Arrange Objects	286
Present Dashboard	288
Print & Export Dashboard	288
Switch Theme	289
Chapter 17 - Automation (Available only in Navicat Premium, Enterprise and Standard Edition)	290
About Automation	290
Create Batch Job (Step 1)	290
Schedule Batch Job (Step 2)	292
Chapter 18 - Backup & Restore	294
About Backup & Restore	294
MySQL / PostgreSQL / SQLite / MariaDB (Available only in Navicat Premium, Enterprise and Standard Edition)	294
About Built-in Backup & Restore Tool	294
Backup	294
Restore	295
Extract SQL	297
Oracle Data Pump (Available only in Navicat Premium, Enterprise and Standard Edition)	298
About Oracle Data Pump	298
Oracle Data Pump Export	298
Oracle Data Pump Import	301
SQL Server Backup & Restore (Available only in Navicat Premium, Enterprise and Standard Edition)	304
About SQL Server Backup & Restore	304
SQL Server Backup	304
SQL Server Restore	306
MongoDump & MongoRestore	308
About MongoDump & MongoRestore	308
MongoDump	308
MongoRestore	308
Redis (Available only in Navicat Premium, Enterprise and Standard Edition)	309
About Built-in Backup & Restore Tool	309
Backup	309
Restore	310
Extract Command	311
Chapter 19 - Server Security	313
About Server Security	313

MySQL / MariaDB User & Role Management	313
User Designer	313
Role Designer	314
Oracle User & Role Management	315
User Designer	315
Role Designer	317
Maintain User	317
PostgreSQL User, Group & Role Management	318
User Designer	318
Group Designer	319
Role Designer	319
SQL Server Login, Role & User Management	321
Login Designer	321
Server Role Designer	323
Database User Designer	323
Database Role Designer	324
Application Role Designer	325
SQLite User Management	326
MongoDB User & Role Management	327
User Designer	327
Role Designer	328
Redis User Management	329
Privilege Manager	330
Chapter 20 - Other Advanced Tools	331
Server Monitor (Available only in Navicat Premium, Enterprise and Standard Edition)	331
Schema Analysis (Available only in Navicat Premium, Enterprise and Standard Edition)	332
Command Monitor (Available only in Navicat Premium, Enterprise and Standard Edition)	333
Virtual Grouping	333
Connection Colorings	334
Find in Database/Schema (Available only in Navicat Premium, Enterprise and Standard Edition)	334
Console	335
Focus Mode (Available only in Navicat Premium, Enterprise and Standard Edition)	335
Share via URI	336
Favorites (Available only in Navicat Premium, Enterprise and Standard Edition)	337
Search Filter	337
Chapter 21 - Configurations	338
Settings	338
General	338
Tabs	339
Code Completion	340
Editor	340
Records	341

Auto Recovery	342
Environment	343
Advanced	344
Chapter 22 - Hot Keys	346
Navicat Hot Keys	346
Chapter 23 - Trace Logs	350
Log Files	350

Chapter 1 - Introduction

About Navicat

Navicat is a multi-connections Database Administration tool allowing you to connect to MySQL, MariaDB, MongoDB, SQL Server, Oracle, PostgreSQL, SQLite, and/or Redis databases, making database administration to multiple kinds of database so easy. It can also manage cloud databases such as Amazon Redshift, Amazon RDS, Alibaba Cloud. Features in Navicat are sophisticated enough to provide professional developers for all their specific needs, yet easy to learn for users who are new to database server. With its well-designed Graphical User Interface(GUI), Navicat lets you quickly and easily create, organize, access and share information in a secure and easy way.

Navicat is available on three platforms - Microsoft Windows, macOS and Linux. It can connect to local/remote servers, providing several utility tools such as Cloud Collaboration, Data Modeling, Data Transfer, Data/Structure Synchronization, Import/Export, Backup/Restore, BI, Data Generation, Data Dictionary, Data Profiling and Automation.

For details, visit our website: <https://www.navicat.com>

System Requirements

Windows

- Microsoft Windows 7, Windows 8, Windows 8.1, Windows 10, Windows 11, Server 2012, Server 2016, Server 2019, Server 2022

macOS

- macOS 11 Big Sur, macOS 12 Monterey, macOS 13 Ventura, macOS 14 Sonoma, macOS 15 Sequoia

Linux

x86_64

- Debian 10, Debian 11, Debian 12, Ubuntu 20.04, Ubuntu 22.04, Ubuntu 24.04, Fedora 38, Fedora 39, Fedora 40, Linux Mint 20, Linux Mint 21, Deepin 20, KylinOS Desktop 10

aarch64

- Debian 11, Debian 12, Ubuntu 22.04, Ubuntu 24.04, Fedora 38, Fedora 39, Fedora 40, Linux Mint 20, Linux Mint 21, KylinOS Desktop 10

Supported On-Premises Databases

- MySQL 3.23 or later
- PostgreSQL 7.3 or later
- Oracle 9i or later

- SQLite 2 and 3
- SQL Server 2000 or later
- MariaDB 5.1 or later
- MongoDB 3.0 or later
- Redis 2.8 or later, Redis Cluster, Redis Sentinel, Microsoft Garnet
- OceanBase Community and Enterprise 3.1.0 or later (Enterprise Oracle Mode is not available in macOS Edition)
- TiDB 7 or later
- Drizzle, OurDelta, Percona Server

Supported Cloud Databases

Amazon AWS

- Amazon Redshift
- Amazon Aurora for MySQL
- Amazon Aurora for PostgreSQL
- Amazon RDS for MySQL
- Amazon RDS for PostgreSQL
- Amazon RDS for Oracle
- Amazon RDS for SQL Server
- Amazon RDS for MariaDB
- Amazon DocumentDB
- Amazon ElastiCache for Redis

Google Cloud

- Google Cloud SQL for MySQL
- Google Cloud SQL for PostgreSQL
- Google Cloud SQL for SQL Server
- Google Memorystore (Redis)

Oracle Cloud

- Oracle Database Cloud Service
- Oracle MySQL Cloud Service

Microsoft

- Microsoft Azure SQL Database
- Microsoft Azure Database for MySQL
- Microsoft Azure Database for PostgreSQL
- Microsoft Azure Database for MariaDB
- Microsoft Azure Cache for Redis

MongoDB Cloud Services

- MongoDB Atlas

Redis Enterprise Cloud

- Redis Enterprise Cloud

Alibaba Cloud

- Alibaba Cloud ApsaraDB RDS for MySQL
- Alibaba Cloud ApsaraDB RDS for PostgreSQL
- Alibaba Cloud ApsaraDB RDS for SQL Server
- Alibaba Cloud ApsaraDB for MongoDB
- Alibaba Cloud ApsaraDB for Redis
- Alibaba Cloud ApsaraDB for OceanBase (MySQL Mode)
- Alibaba Cloud PolarDB for MySQL
- Alibaba Cloud PolarDB for PostgreSQL
- Alibaba Cloud PolarDB for Xscale

Tencent Cloud

- Tencent Cloud TencentDB for MySQL
- Tencent Cloud TencentDB for PostgreSQL

- Tencent Cloud TencentDB for SQL Server
- Tencent Cloud TencentDB for MariaDB
- Tencent Cloud TencentDB for MongoDB
- Tencent Cloud TencentDB for Redis

Huawei Cloud

- Huawei Cloud RDS for MySQL
- Huawei Cloud RDS for PostgreSQL
- Huawei Cloud RDS for SQL Server
- Huawei Cloud Document Database Service
- Huawei Cloud Distributed Cache Service for Redis

Installation

We strongly suggest that you shut down any opened applications. This will help ensure a smooth installation.

Installation for Download Version

1. Download Navicat macOS version.
2. Open the **.dmg** file.
3. Drag Navicat to your Applications folder to install.

Installation for CD Version

1. Load the Navicat CD Installation disk into the CD-ROM drive.
2. Open the **.dmg** file.
3. Drag Navicat to your Applications folder to install.

Registration

When the trial period is finished, Navicat requires a license key or a subscription plan to continue using the features.

Note: Perpetual License and Subscription Plan cannot be used at the same Navicat. Before changing the registration method, you need to deactivate the license key or sign out your Navicat ID.

Perpetual License

If you have purchased a perpetual license, you will receive a license key for activating Navicat.

In the **Perpetual License** section, paste your license key (16 digits) and click the **Activate** button. Navicat contacts our licensing server to activate the license key. If the activation process is successful, the license key details are displayed.

Manual Activation

Manual activation is available when your computer does not have an internet connection. You will need another computer with an internet connection to complete this activation process.

1. If the online activation is failed, click **Manual Activation**.
2. Copy the Request Code in the **Copy the Request Code Here:** box.
3. Open web browser on a computer with an internet connection and then go to https://customer.navicat.com/manual_activate.php.
4. Paste/Enter the Request Code into the left box.
5. Click **Get Activation Code**.
6. Copy the generated Activation Code in the right box.
7. Go back to the computer where you are activating Navicat.
8. Paste the Activation Code into the **Paste the Activation Code Here:** box.
9. Click **Activate**.

Subscription Plan

If you have subscribed a plan, you can sign in your Navicat ID to use Navicat during the subscription term.

Note: Navicat ID is the Email address that you used to subscribe the plan.

In the **Subscription** section, provide your **Navicat ID** and **Password**. After signed in, the subscription plan details are displayed.

Navicat contacts our licensing server once per hour to auto reload the plan by default. If you have updated your plan in the portal site, you can use the **Reload Plan** button to force reloading the new plan.

Note: Each Navicat ID can connect to only one Navicat. If you sign in your Navicat ID in another Navicat, you will be signed out from the current Navicat.

Migration / Upgrade

Migrate Navicat to a new computer

1. In Navicat, choose **File -> Export Connections**. The exported file (.ncx) contains all your connection settings.

2. Backup the exported file (.ncx).
3. In Navicat, choose **Navicat XXX -> Registration**.
4. [Perpetual License] Click **Deactivate** to online deactivate the license key.
5. [Subscription Plan] Click **Sign Out** to sign out your Navicat ID.
6. Uninstall Navicat from the existing computer.
7. Re-install Navicat in the new computer.
8. Open Navicat and choose **File -> Import Connections** in the new computer to import the connection settings (.ncx).

When a new connection is being established, Navicat will create a subfolder under [Settings Location](#). Most files are stored within this subfolder. To look for the path, control-click the connection and select **Edit Connection -> Advanced -> Settings Location**.

Moreover, all your saved profiles are stored under the default path, e.g. ~/Library/Application Support/PremiumSoft CyberTech/Navicat CC/Navicat Premium/Profiles.

Upgrade Navicat

If you want to upgrade an installed copy of Navicat to the latest release, please choose **Navicat XXX -> Check for Updates** to start the Updater. It will automatically check your installed version. If there is a new version, simply follow the steps in the Updater to upgrade your Navicat. It will replace your previous Navicat and your current settings will remain unchanged.

Or, you can submit your registered email address on the [Customer Center](#) to download the latest version installer.

End-User License Agreement

Note: For the License Agreement of Navicat Cloud service, please click [here](#).

IMPORTANT: THIS SOFTWARE END USER LICENSE AGREEMENT ("EULA") IS A LEGAL AGREEMENT BETWEEN YOU (EITHER AN INDIVIDUAL OR, IF PURCHASED OR OTHERWISE ACQUIRED BY OR FOR AN ENTITY, AN ENTITY) AND PREMIUMSOFT CYBERTECH LTD..READ IT CAREFULLY BEFORE COMPLETING THE INSTALLATION PROCESS AND USING THE SOFTWARE. IT PROVIDES A LICENSE TO USE THE SOFTWARE AND CONTAINS WARRANTY INFORMATION AND LIABILITY DISCLAIMERS. BY INSTALLING AND USING THE SOFTWARE, YOU ARE CONFIRMING YOUR ACCEPTANCE OF THE SOFTWARE AND AGREEING TO BECOME BOUND BY THE TERMS OF THIS AGREEMENT. IF YOU DO NOT AGREE TO BE BOUND BY THESE TERMS, THEN DO NOT INSTALL THE SOFTWARE AND RETURN THE SOFTWARE TO YOUR PLACE OF PURCHASE. THIS EULA SHALL APPLY ONLY TO THE SOFTWARE SUPPLIED BY PREMIUMSOFT CYBERTECH LTD. HERewith REGARDLESS OF WHETHER OTHER SOFTWARE IS REFERRED TO OR DESCRIBED HEREIN.

1. Definitions

- a. "Non-commercial Version" means a version of the Software, so identified, for use by i) the individual who is a natural person and not a corporation, company, partnership or association or other entity or organization (ii) the individual who is a student, faculty or staff member at an educational institution, and (iii) staff of a non-profit organization or charity organization only. For purposes of this definition, "educational institution" means a public or private school, college, university and other post secondary educational establishment. A non-profit organization is an organization whose primary objective is to support an issue or matter of private interest or public concern for non-commercial purposes.
- b. "Not For Resale (NFR) Version" means a version, so identified, of the Software to be used to review and evaluate the Software, only.
- c. "PremiumSoft" means PREMIUMSOFT CYBERTECH LTD. and its licensors, if any.
- d. "Software" means only the PremiumSoft software program(s) and third party software programs, in each case, supplied by PremiumSoft herewith, and corresponding documentation, associated media, printed materials, and online or electronic documentation.
- e. "Unregistered version", "Trial version" or "Demo version" means an unregistered copy of the SOFTWARE ("UNREGISTERED SOFTWARE") which may be used by the USER for evaluation purposes for a period of fourteen (14) days following the initial installation of the UNREGISTERED SOFTWARE. At the end of the trial period ("TRIAL PERIOD"), the USER must either register the SOFTWARE or remove it from his system. The UNREGISTERED SOFTWARE may be freely copied and distributed to other users for their evaluation.
- f. "Navicat Premium Lite" means a free-to-use version of the Software with limited features, identified as "Lite".

2. License Grants

The licenses granted in this Section 2 are subject to the terms and conditions set forth in this EULA:

- a. Subject to Section 2(b), you may install and use the Software on a single computer; OR install and store the Software on a storage device, such as a network server, used only to install the Software on your other computers over an internal network, provided you have a license for each separate computer on which the Software is installed and run. Except as otherwise provided in Section 2(b), a license for the Software may not be shared, installed or used concurrently on different computers.
- b. In addition to the single copy of the Software permitted in Section 2(a), the primary user of the computer on which the Software is installed may make a second copy of the Software and install it on either a portable computer or a computer located at his or her home for his or her exclusive use, provided that:
 - A. the second copy of the Software on the portable or home computer (i) is not used at the same time as the copy of the Software on the primary computer and (ii) is used by the primary user solely as allowed for such version or edition (such as for educational use only),
 - B. the second copy of the Software is not installed or used after the time such user is no longer the primary user of the primary computer on which the Software is installed.

- c. In the event the Software is distributed along with other PremiumSoft software products as part of a suite of products (collectively, the "Studio"), the license of the Studio is licensed as a single product and none of the products in the Studio, including the Software, may be separated for installation or use on more than one computer.
- d. You may make one copy of the Software in machine-readable form solely for backup purposes. You must reproduce on any such copy all copyright notices and any other proprietary legends on the original copy of the Software. You may not sell or transfer any copy of the Software made for backup purposes.
- e. You agree that PremiumSoft may audit your use of the Software for compliance with these terms at any time, upon reasonable notice. In the event that such audit reveals any use of the Software by you other than in full compliance with the terms of this Agreement, you shall reimburse PremiumSoft for all reasonable expenses related to such audit in addition to any other liabilities you may incur as a result of such non-compliance.
- f. Your license rights under this EULA are non-exclusive.

3. License Restrictions

- a. Other than as set forth in Section 2, you may not make or distribute copies of the Software, or electronically transfer the Software from one computer to another or over a network.
- b. You may not alter, merge, modify, adapt or translate the Software, or decompile, reverse engineer, disassemble, or otherwise reduce the Software to a human-perceivable form.
- c. Unless otherwise provided herein, you may not rent, lease, or sublicense the Software.
- d. Other than with respect to a Trial / Demo Version, Lite Version or a Not For Resale Version of the Software, you may permanently transfer all of your rights under this EULA only as part of a sale or transfer, provided you retain no copies, you transfer all of the Software (including all component parts, the media and printed materials, any upgrades, this EULA, the serial numbers, and, if applicable, all other software products provided together with the Software), and the recipient agrees to the terms of this EULA. If the Software is an upgrade, any transfer must include all prior versions of the Software from which you are upgrading. If the copy of the Software is licensed as part of the whole Studio (as defined above), the Software shall be transferred only with and as part of the sale or transfer of the whole Studio, and not separately. You may retain no copies of the Software. You may not sell or transfer any Trial / Demo Version, Lite Version or Not For Resale Version of the Software.
- e. Unless otherwise provided herein, you may not modify the Software or create derivative works based upon the Software.
- f. Non-commercial Versions of the Software may not be used for, or distributed to any party for, any commercial purpose.
- g. Unless otherwise provided herein, you shall not
 - A. in the aggregate, install or use more than one copy of the Trial / Demo Version of the Software,

- B. download the Trial / Demo Version of the Software under more than one username,
 - C. alter the contents of a hard drive or computer system to enable the use of the Trial / Demo Version of the Software for an aggregate period in excess of the trial period for one license to such Trial / Demo Version,
 - D. disclose the results of software performance benchmarks obtained using the Trial / Demo Version or Lite Version to any third party without PremiumSoft prior written consent, or
 - E. use the Trial / Demo Version of the Software for a purpose other than the sole purpose of determining whether to purchase a license to a commercial or education version of the software; provided, however, notwithstanding the foregoing, you are strictly prohibited from installing or using the Trial / Demo Version or Lite Version of the Software for any commercial training purpose.
- h. For Navicat Premium Lite: For avoidance of doubt, Navicat Premium Lite is licensed, not sold. Under this EULA, PremiumSoft grants you the right to 1) download [one copy] of the software, and 2) install and run [one instance] of the software on your [one device], whether physical or virtual with an internal storage device capable of running the software, so long as you comply with all the terms of this EULA.
- If you were in possession of multiple software versions, you may only install and run [one] of those versions at a time. If you use the software on more than one physical or virtual device, you must obtain a separate license for each instance.
- [Commercial Use]
- The number of users at any time within a business, whether incorporated or not, shall not exceed [five persons]. To use the software on more than one device, you are required to obtain a dedicated license and you may allow up to [five other devices] to access the software installed on the licensed device for commercial use.
- [Non-Commercial Use]
- Users qualified for PremiumSoft's Non-Commercial Licensing Program, subject to the conditions of the program as detailed in [Navicat Non-Commercial Licensing Program](http://www.navicat.com/en/store/non-commercial) (www.navicat.com/en/store/non-commercial), are granted the right to download, install, run, and use the software.
- i. You may only use the Not for Resale Version of the Software to review and evaluate the Software.
 - j. You may receive the Software in more than one medium but you shall only install or use one medium. Regardless of the number of media you receive, you may use only the medium that is appropriate for the server or computer on which the Software is to be installed.
 - k. You may receive the Software in more than one platform but you shall only install or use one platform.
 - l. You shall not use the Software to develop any application having the same primary function as the Software.
 - m. In the event that you fail to comply with this EULA, PremiumSoft may terminate the license and you must destroy all copies of the Software (with all other rights of both parties and all other provisions of this EULA surviving any such termination).
 - n. This program may include Oracle Instant Client (OCI). You agree that you shall

1. not use of the Oracle Instant Client to the business operations;
2. not assign, give, or transfer the Oracle Instant Client or an interest in them to another individual or entity;
 - a. make the Programs available in any manner to any third party for use in the third party's business operations; and
 - b. title to the Programs from passing to the end user or any other party;
3. not reverse engineer, disassemble or decompilation the Oracle Instant Client and duplicate the Programs except for a sufficient number of copies of each Program for your licensed use and one copy of each Program media;
4. discontinue use and destroy or return to all copies of the Oracle Instant Client and documentation after termination of the Agreement;
5. not publish any results of benchmark tests run on the Programs;
6. comply fully with all relevant export laws and regulations of the United States and other applicable export and import laws to assure that neither the Oracle Instant Client, nor any direct product thereof, are exported, directly or indirectly, in violation of applicable laws;
7. allow PremiumSoft to audit your use of the Oracle Instant Client;

4. Upgrades

If this copy of the Software is an upgrade from an earlier version of the Software, it is provided to you on a license exchange basis. You agree by your installation and use of such copy of the Software to voluntarily terminate your earlier EULA and that you will not continue to use the earlier version of the Software or transfer it to another person or entity unless such transfer is pursuant to Section 3.

5. Ownership

The foregoing license gives you limited license to use the Software. PremiumSoft and its suppliers retain all rights, title and interest, including all copyright and intellectual property rights, in and to, the Software (as an independent work and as an underlying work serving as a basis for any application you may develop), and all copies thereof. All rights not specifically granted in this EULA, including Federal and International Copyrights, are reserved by PremiumSoft and its suppliers.

6. LIMITED WARRANTY AND DISCLAIMER

- a. Except with respect to Trial / Demo Version, Lite Version and Not For Resale Version of the Software, PremiumSoft warrants that, for a period of thirty (30) days from the date of delivery (as evidenced by a copy of your receipt): the physical media on which the Software is furnished will be free from defects in materials and workmanship under normal use. The Software is provided "as is". PremiumSoft makes no warranties, express or implied, arising from course of dealing or usage of trade, or statutory, as to any matter whatsoever.

- b. PremiumSoft provides no remedies or warranties, whether express or implied, for Trial / Demo version, Lite version and the Not for Resale version of the Software. Trial / Demo version, Lite version and the Not for Resale version of the Software are provided "as is".
- c. Except as set Forth in the foregoing limited warranty with respect to software other than Trial/ Demo version, Lite version and Not for Resale version, PremiumSoft and its suppliers disclaim all other warranties and representations, whether express, implied, or otherwise, including the warranties of merchantability or fitness for a particular purpose. Also, there is no warranty of non-infringement and title or quiet enjoyment. PremiumSoft does not warrant that the Software is error-free or will operate without interruption. The Software is not designed, intended or licensed for use in hazardous environments requiring fail-safe controls, including without limitation, the design, construction, maintenance or operation of nuclear facilities, aircraft navigation or communication systems, air traffic control, and life support or weapons systems. PremiumSoft specifically disclaims any express or implied warranty of fitness for such purposes.
- d. If applicable law requires any warranties with respect to the Software, all such warranties are limited in duration to thirty (30) days from the date of delivery.
- e. No oral or written information or advice given by PremiumSoft, its dealers, distributors, agents or employees shall create a warranty or in any way increase the scope of ANY warranty PROVIDED HEREIN.

7. LIMITATION OF LIABILITY

(a) Neither PremiumSoft nor its suppliers shall be liable to you or any third party for any indirect, special, incidental, punitive or consequential damages (including, but not limited to, damages for the inability to use equipment or access data, loss of business, loss of profits, business interruption or the like), arising out of the use of, or inability to use, the Software and based on any theory of liability including breach of contract, breach of warranty, tort (including negligence), product liability or otherwise, even if PremiumSoft or its representatives have been advised of the possibility of such damages.

8. Third Party Software

The Software may contain third party software which requires notices and/or additional terms and conditions. By accepting this EULA, you are also accepting the additional terms and conditions of the third party software.

9. General

No PremiumSoft dealer, agent or employee is authorized to make any amendment to this EULA.

This EULA contains the complete agreement between the parties with respect to the subject matter hereof, and supersedes all prior or contemporaneous agreements or understandings, whether oral or written. You agree that any varying or additional terms contained in any purchase order or other written notification or document issued by you in relation to the Software licensed hereunder shall be of no effect. The failure or delay of PremiumSoft to exercise any of its rights under this EULA or upon any breach of this EULA shall not be deemed a waiver of those rights or of the breach.

If any provision of this EULA shall be held by a court of competent jurisdiction to be contrary to law, that provision will be enforced to the maximum extent permissible, and the remaining provisions of this EULA will remain in full force and Effect.

10. Basis of Bargain

The Limited Warranty and Disclaimer and Limited Liability set forth above are fundamental elements of the basis of the agreement between PremiumSoft and you. PremiumSoft would not be able to provide the Software on an economic basis without such limitations. Such Limited Warranty and Disclaimer and Limited Liability inure to the benefit of PremiumSoft's licensors.

11. Term

By downloading and/or installing this SOFTWARE, the Licensor agrees to the terms of this EULA.

This license is effective until terminated. Licensor has the right to terminate your License immediately if you fail to comply with any term of this License.

"as is". Licensor makes no warranties, express or implied, arising from course of dealing or usage of trade, or statutory, as to any matter whatsoever. In particular, any and all warranties or merchantability, fitness for a particular purpose or non-infringement of third party rights are expressly excluded.

12. License Termination

Without prejudice to any other rights, PremiumSoft may terminate this EULA if you fail to comply with the terms and conditions of this EULA. In such event, you must destroy all copies of the software and all of its component parts.

13. Governing Law

This License will be governed by the laws in force in Hong Kong. You hereby consent to the non-exclusive jurisdiction and venue sitting in Hong Kong to resolve any disputes arising under this EULA.

Should you have any questions concerning the validity of this License, please contact: licensing@navicat.com. If you desire to contact the Licensor for any other reason, please contact support@navicat.com.


PremiumSoft and other trademarks contained in the Software are trademarks or registered trademarks of PremiumSoft CyberTech Ltd. in the United States and/or other countries. Third party trademarks, trade names, product names and logos may be the trademarks or registered trademarks of their respective owners. You may not remove or alter any trademark, trade names, product names, logo, copyright or other proprietary notices, legends, symbols or labels in the Software. This EULA does not authorize you to use PremiumSoft or its licensors names or any of their respective trademarks.

Chapter 2 - User Interface

Main Window

The Main Window consists of several toolbars and panes for you to work on connections, database objects and advanced tools.

Hint: Navicat has added support for the system-wide dark mode.



1 Main Toolbar

The Main Toolbar allows you to access basic objects and features, such as connections, users, tables, collections, backup, automation and more. If the Main Toolbar is hidden, choose **View -> Show Toolbar** from the menu bar.

2 Navigation Pane

The Navigation Pane is the basic way to navigate with connections, databases and database objects. If the Navigation Pane is hidden, choose **View -> Navigation Pane -> Show Navigation Pane** from the menu bar.



3 Tab Bar

The Tab Bar allows you to switch among the tabbed windows on the Object Pane. You can choose to always display pop-ups on a new tab, or to always display them in a new window. If you have multiple tabs open, you can use **COMMAND-{} or COMMAND-{} to easily switch to other tabs**. Control-click a tab to add it to favorite list or startup list. See also [Settings](#).

4 Object Toolbar

The Object Toolbar provides other controls that you can use to manipulate the objects.

5 Object Pane

The Object Pane displays a list of objects (such as tables, collections, views, queries) and the tabbed window forms. Use the  **Detail** and  **ER Diagram** buttons to change the view of the Objects tab.

⑥ Information Pane

The Information Pane shows the detailed object information, project activities, the DDL of database objects, object dependencies, membership of users/roles and preview. If the Information Pane is hidden, choose **View -> Information Pane -> Show Information Pane** from the menu bar.

⑦ Status Bar

The Status Bar displays the current window's status information. To view or hide the Status Bar, choose **View -> Show Status Bar** from the menu bar.

Navigation Pane

The Navigation pane employs tree structure which allows you to take action upon the database and their objects through their pop-up menus quickly and easily. If the **Show objects under schema in navigation pane** option is checked at the [Settings](#) window, all database objects are also displayed in the pane. To connect to a database or schema, simply double-click it in the pane.

After logged in [Navicat Cloud](#) or [On-Prem Server](#), you can find it in the Navigation pane, and all connections stored locally will be located under the **My Connections** section.

Table elements, such as fields, indexes and foreign keys, are display under each table. Click the arrow to the left of the table name to expand the list. If the elements are hidden, enable the **Show objects under table** option in the [Settings](#) window.



You can simply rename a field by using the pop-up menu, or you can double-click an element to open the table designer.

If you want to hide the group structure in the Navigation pane, choose **View -> Navigation Pane -> Flatten Connection**.

If the Navigation pane is hidden, choose **View -> Navigation Pane -> Show Navigation Pane**.

Filter Connections

Entering a search string in the **Search** text box will only show items containing the string. All groups, opened connections and objects that containing search result will also automatically expand to show the filtered results.

The  and  icons on the right of the text box let you quickly filter for specific connection types and venders, active objects or starred connections.

Object Pane

In the **Objects** tab, you can use the  **Detail** and  **ER Diagram** buttons to change the object view.

If you want to hide the group structure in Detail view, choose **View -> Flatten Object List** from the menu bar.


Detail View

Detail view shows the name and several properties of objects in columns. To change the display columns of properties, choose **View -> Choose Columns** from the menu bar and choose display columns for different objects from the pop-up window.

ER Diagram View (Available only in Navicat Premium, Enterprise and Standard Edition)

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server and MariaDB. Only tables provide ER Diagram view.

An ER diagram will be generated automatically if the selected database/schema contains tables. ER diagram files are stored under [Settings Location](#).



1 Diagram Canvas

Display table fields and relationships between tables in a database/schema graphically.

Add a Foreign Key

Click  from the object toolbar. Drag and drop a field from the child table to the parent table.

Edit or Delete a Foreign Key

Control-click a relation line and select **Design Foreign Key** or **Delete Foreign Key** from the pop-up menu.

Note: Double-click a table in the ER Diagram view will open the Table Designer, while double-click a table in the List or Detail view will open the Table Viewer.

2 Overview









To zoom in or zoom out the selected area of the diagram, adjust the slider of the Overview. Same effect can be achieved with keyboard shortcuts:

Zoom In: [COMMAND-Mousewheel up]

Zoom Out: [COMMAND-Mousewheel down]

Zoom Reset: [COMMAND-0]





③ Bottom Toolbar








Button	Description
	Refresh - Refresh the ER diagram. Regenerate ER Diagram - Regenerate the ER diagram with using the auto layout feature.
	Switch the cursor to the Select mode.
	Switch the cursor to the hand mode for moving the diagram. Or, you can press and hold the SPACE key, then move the diagram.
	Add a relation between two table fields. Click this button, and then drag and drop a field from the child table to the parent table.
	Set the color of the selected tables or relations.
	Automatically arrange all tables or selected tables on the canvas.
	Export the ER diagram to a PNG file.
	Preview the diagram in a fullscreen mode.
Size	Select a paper size from the drop-down list. The corresponding paper size will reflect in the Overview pane.

Information Pane

The Information Pane shows the detailed object information, project activities, the DDL of database objects, object dependencies, membership of users/roles and preview. If the Information Pane is hidden, choose **View -> Information Pane -> Show Information Pane** from the menu bar.

You can select any connections, objects or projects, and then select the corresponding buttons on the Information Pane.

Button	Description
	General - Show the general information of the object/project.
	Preview - Show the SQL statements in the query.
	DDL - Show the DDL statements of the object. Press COMMAND-F to open the search box.
	Using - Show the objects that the selected object depends on. Objects - Show the objects in the tablespace.

	Member Of - Show the roles that the user or the role assigned to.
	Used By - Show the objects that depend on the selected object. Members - Show the members of the role.
	Code Snippet - Show all built-in and custom code snippets .
	Identifiers - Show all available tables, collections, views or fields in the selected database or schema. Field - Show the information of the selected field in Table Viewer.
	Privileges - Show the privileges granted to the user.
	Project - Show the project members and the project activities done by the members. Click + to add members to the project.
	Type Color - Set the color of particular types for highlighting cells in Grid View . (Available only for MongoDB)
	Pub/Sub Info - Show which channels are active on the Redis server.

Chapter 3 - Collaboration

About Collaboration

Navicat allows you to synchronize connection settings, queries, aggregation pipelines, snippets, model workspaces, BI workspaces and virtual group information from Navicat, other Navicat family members, different machines and different platforms. You can use Navicat Cloud to host the files. Or, if you have installed our another product, Navicat On-Prem Server, in your environment, you can hosts everything in-house.

Our collaboration feature allows you to give your teammates access to your projects when they log into their accounts. That way, you and your teammates can work on the same project without revealing your username and password. You can even choose to restrict the type of access your teammates have to your project.

Manage Cloud

Navicat Cloud

Navicat Cloud is a cloud service provided by PremiumSoft for synchronizing connection settings, queries, aggregation pipelines, snippets, model workspaces, BI workspaces and virtual group information.

Navicat Cloud could not connect and access your databases. By which it means, it could only store your connection settings, queries, aggregation pipelines, snippets, model workspaces, BI workspaces and virtual group information; your database passwords and data (e.g. tables, views, etc) will not be stored to Navicat Cloud.

Note: You can only sign in to one Navicat Cloud account in the software. PremiumSoft will keep all synchronized files strictly confidential, and all employees are prohibited from viewing/accessing content of files you may store in your Navicat Cloud account.

Create Navicat Cloud Account

1. In the menu bar, choose **Navicat XXX -> Manage Cloud**.
2. In the Manage Cloud window, select **Navicat Cloud**.
3. Click **Create Navicat ID**.
4. Enter the required information and click **Sign Up**. A verification email will send to your email address.
5. Click the link in the email to verify the new account.

Hint: You can sign in with the same Navicat ID you use for the Navicat Customer Center.

Sign In Navicat Cloud

1. In the menu bar, choose **Navicat XXX -> Manage Cloud**.
2. In the Manage Cloud window, select **Navicat Cloud**.

3. Enter your **Navicat ID** and **Password**.
4. Click **Sign In**.
5. If you enabled two-step verification in [Navicat Cloud Portal](#), a code will be sent to your phone via your mobile app. Enter the received code to sign in.

Sign Out Navicat Cloud

1. In the main window, control-click **Navicat Cloud** and select **Close All Connections** to close all connections under Navicat Cloud.
2. At the top right, click your avatar.
3. In the Manage Cloud window, select **Navicat Cloud**.
4. Click **Sign Out**.

View Usage

1. At the top right, click your avatar.
2. In the Manage Cloud window, select **Navicat Cloud**.
3. Your usage and current plan will be shown.

Change Your Picture

1. At the top right, click your avatar.
2. In the Manage Cloud window, select **Navicat Cloud**.
3. Click your avatar.
4. Choose an image file.

Manage Your Account

You can change your password, enable Two-Step Verification, upgrade Cloud Plan, etc in [Navicat Cloud Portal](#).

1. At the top right, click your avatar.
2. In the Manage Cloud window, select **Navicat Cloud**.
3. Click **Manage Account**.
4. A web browser will automatically open up to Navicat Cloud Portal.

On-Prem Server

Navicat On-Prem Server is an on-premise solution that provides you with the option to host a cloud environment for storing Navicat objects (connection settings, queries, aggregation pipelines, snippets, model workspaces, BI workspaces and virtual group information) internally at your location.

Before you can add an On-Prem Server, you must first set up Navicat On-Prem Server in your environment.

Note: You can add multiple On-Prem Server in the software.

Add New On-Prem Server

1. In the menu bar, choose **Navicat XXX -> Manage Cloud**.
2. In the Manage Cloud window, click **+ New On-Prem Server -> New On-Prem Server**.
3. Enter your On-Prem Server login information.

Option	Description
Host	The host name or IP address of your On-Prem Server.
Port	The port number of your On-Prem Server.
Verify Server Certificate	Enable this option to verify the server certificates.
Enable Push Synchronization	Navicat receives a silent push notification whenever its files stored in your On-Prem Server changes.

4. Click **OK**.

Add New On-Prem Server with URI

1. In the menu bar, choose **Navicat XXX -> Manage Cloud**.
2. In the Manage Cloud window, click **+ New On-Prem Server -> New On-Prem Server with URI**.
3. Paste your On-Prem Server URI.
4. Click **OK**.

Note: The URI can be copied from your On-Prem Server portal site.

Sign In On-Prem Server

1. In the menu bar, choose **Navicat XXX -> Manage Cloud**.
2. In the Manage Cloud window, select the On-Prem Server.
3. Enter your **Username** and **Password**.
4. Click **Sign In**.

5. If you enabled two-step verification, a code will be sent to you via the verification method you have selected. Enter the received code to sign in.

Sign Out On-Prem Server

1. In the main window, control-click the On-Prem Server and select **Close All Connections** to close all connections in your server.
2. At the top right, click your avatar.
3. In the Manage Cloud window, select the On-Prem Server.
4. Click **Sign Out**.

Edit On-Prem Server

1. In the main window, control-click the On-Prem Server and select **Close All Connections** to close all connections in your server.
2. At the top right, click your avatar.
3. In the Manage Cloud window, select the On-Prem Server.
4. Click **Sign Out**.
5. Control-click your server and select **Edit On-Prem Server**.
6. Edit the On-Prem Server information.
7. Sign in your server.

Rename On-Prem Server

1. In the main window, control-click the On-Prem Server and select **Close All Connections** to close all connections in your server.
2. At the top right, click your avatar.
3. In the Manage Cloud window, select the On-Prem Server.
4. Click **Sign Out**.
5. Control-click your server and select **Rename**.
6. Enter the name to describe your On-Prem Server.
7. Sign in your server.

Remove On-Prem Server

1. In the main window, control-click the On-Prem Server and select **Close All Connections** to close all connections in your server.
2. At the top right, click your avatar.
3. In the Manage Cloud window, select the On-Prem Server.
4. Click **Sign Out**.
5. Control-click your server and select **Remove On-Prem Server**.
6. Click **Delete**.

View Usage

1. At the top right, click your avatar.
2. In the Manage Cloud window, select the On-Prem Server.
3. Your usage will be shown.

Change Your Picture

1. At the top right, click your avatar.
2. In the Manage Cloud window, select the On-Prem Server.
3. Click your avatar.
4. Choose an image file.

Manage Your Account

You can change your password, enable Two-Step Verification, etc in your On-Prem Server web portal.

1. At the top right, click your avatar.
2. In the Manage Cloud window, select the On-Prem Server.
3. Click **Manage Account**.
4. A web browser will automatically open up to your On-Prem Server web portal.

Push Synchronization

Push Synchronization enables Navicat to receive a silent push notification whenever the files stored in Navicat Cloud or On-Prem Server changes.

Enable Push Synchronization

1. At the top right, click your avatar.
2. In the Manage Cloud window, control-click Navicat Cloud or your On-Prem Server.
3. Turn on **Enable Push Synchronization**.

Disable Push Synchronization

1. At the top right, click your avatar.
2. Turn off **Enable Push Synchronization**.

Cache and Local Copies

When you logged into Navicat Cloud or your On-Prem Server, Navicat saves the cloud object files and some information in the local computer. The cache and local copies use to make sure your changes are saved in the cloud.

Clear Cache and Local Copies

1. At the top right, click your avatar.
2. In the Manage Cloud window, select Navicat Cloud or your On-Prem Server.
3. Click **Sign Out**.
4. Control-click Navicat Cloud or your On-Prem Server and select **Clear Cache and Local Copies**.
5. Click **Clear**.

Show In Finder

1. In the main window, select Navicat Cloud or your On-Prem Server.
2. Open your project, connection, database and/or schema.
3. Click the Query, Model or BI icon.
4. Control-click anywhere in the Objects tab and select **Show In Finder**.

Projects

Work With Projects

A project is a way to structure and organize Navicat objects. You can put related objects in one project, and then share the project with other accounts for collaboration if necessary.

Create New Projects

1. In the main window, control-click **Navicat Cloud** or your On-Prem Server.

2. Select **New Project**.
3. Enter the name of the new project.
4. Click **OK**.

Manage Existing Projects

To rename a project

1. In the main window, control-click the project and select **Rename**.
2. Enter a new project name.

Note: Only the project owner and the members with the *Can Manage & Edit* right can rename the project.

To delete a project

1. In the main window, control-click the project and select **Delete Project**.
2. Click **Delete**.

Note: Only the project owner can delete the project.

Note: Before you delete the project, you must remove all objects in the project.

To quit a project

1. In the main window, control-click the project and select **Quit Project**.
2. Click **Quit**.

Manage Members

Add Members

1. In the main window, control-click the project and select **Manage Members**.
2. Click **Add Members**.
3. [Navicat Cloud] Enter the member's Navicat ID and press ENTER.
4. [On-Prem Server] Check the boxes of the users that you want to add.
5. Select the member right.
6. Click **Add**.

Member Rights	Privileges
Can Manage & Edit	Read Objects, Write Objects, Manage Members and Rename

	Projects
Can Edit	Read Objects and Write Objects
Can View	Read Objects

Manage Existing Members

To edit the right of a member

1. In the main window, control-click the project and select **Manage Members**.
2. Use the drop-down menu next to the member to change the right.
3. Click **Apply**.

To remove a member from a project

1. In the main window, control-click the project and select **Manage Members**.
2. Click the **X** icon next to the member.
3. Click **Apply**.


Chapter 4 - Connection

About Connection

To start working with your server in Navicat, you should first establish a connection or several connections using the Connection window. If you are new to the server or 'Net in general' and are not quite sure how things work, you may want to look at:


- [MySQL User Manual](#)
- [Oracle Database Documentation](#)
- [PostgreSQL User Manual](#)
- [SQLite User Manual](#)
- [Microsoft SQL documentation](#)
- [MariaDB Documentation](#)
- [MongoDB Manual](#)
- [Redis Documentation](#)

Create Connection

1. In the main window, click  **Connection**.
2. In the New Connection window, select your server type and click **Next**.
3. Enter the necessary information.
4. Click **OK**.

Note: Navicat authorizes you to make connection to remote servers running on different platforms (i.e. Windows, macOS, Linux and UNIX), and supports PAM, Kerberos and LDAP authentication. Kerberos is only available in Navicat Premium, Enterprise and Standard Edition.

Create Connection with URI

1. In the main window, click  **Connection**.
2. In the New Connection window, click **New Connection with URI**.
3. Paste your Navicat URI or MongoDB URI.
4. Click **Apply**.

5. Navicat automatically fills out the options in the connection window. Modify your connection information if necessary.
6. Click **OK**.

Hint: The Navicat URI can be copied from the Edit Connection window.

Edit Connection Settings

1. In the main window, control-click your connection and select **Edit Connection**.
2. In the Edit Connection window, modify your connection information.
3. Click **OK**.

Hint: You can view / copy your Navicat URI or MongoDB URI by clicking **URI**.

Move / Copy Connection To Project

If you have logged in to Navicat Cloud or On-Prem Server, you can synchronize the connection in My Connections to a project.

1. Control-click a connection under **My Connections** and select **Move Connection To** or **Copy Connection To**.
2. Select an existing project or create a new project.
3. Choose whether to include all queries and virtual groups in the connection and click **OK**.
4. The connection will be moved or copied to the project.

Hint: You can move / copy a connection in a project to My Connections in a similar way.

Flush MySQL/MariaDB Connection

To clear or reload various internal caches, flush tables, or acquire locks, control-click your connection in the Navigation pane and select **Flush** and choose the flush option. You must have the [RELOAD](#) privilege to use this feature.

Manage Azure SQL Database Firewall Rules

You cannot connect to Azure SQL Database until you have granted your client IP access. To access Azure SQL Database from your computer, ensure that your firewall allows outgoing TCP communication on TCP port 1433. You must have at least one firewall rule before you can connection to Azure SQL Database.

To manage the Firewall Rule settings, control-click your Azure SQL Database connection in the Navigation pane and select **SQL Azure Firewall Rules**. Add a new rule by providing an IP address range.

Testing Account

Navicat provides evaluated accounts for testing purpose.

MySQL

- Host: server1.navicat.com
- Port: 4406
- User Name: navicat
- Password: testnavicat

PostgreSQL

- Host: server1.navicat.com
- Port: 5432
- Initial Database: HR
- User Name: navicat
- Password: testnavicat

General Settings

RDBMS

To successfully establish a new connection to local/remote server - no matter via SSL, SSH or HTTP, set the database login information in the General tab. If your Internet Service Provider (ISP) does not provide direct access to its server, Secure Tunneling Protocol (SSH) / HTTP is another solution.

Note: The following options depend on the connection server type and sort in ascending order.

Add To

After you logged in [Navicat Cloud](#) or [On-Prem Server](#), you can choose to save the connection to My Connections or a project.

Authentication

SQL Server Authentication	Use login records to validate the connection. Users must provide their server login: User Name and Password .
Windows Authentication	When a user connects through a Windows user account, SQL Server validates the account name and password using the Windows principal token in the operating system.

Connection Name

Enter a friendly name to best describe your connection.

Connection Type

Basic	In Basic mode, it connects to Oracle through the Oracle Call Interface (OCI). Enter the Host and Port . Set the Service Name/SID which the user connects when making connection. Select the corresponding radio button.
TNS	In TNS mode, it connects to Oracle server using an alias entry from a tnsnames.ora file through the Oracle Call Interface (OCI). User needs to provide the Net Service Name .

OCI is an application programming interface that allows an application developer to use a third-generation language's native procedure or function calls to access the Oracle database server and control all phases of SQL statement execution. OCI is a library of standard database access and retrieval functions in the form of a dynamic-link library. See also: [Environments](#)

Database File

Specify the initial database file. If the HTTP Tunnel is enabled, you need to enter an absolute file path of the database file in your web server.

Endpoint

The Endpoint for connecting to the Amazon Web Services instance.

Host

A host name where the database is situated or the IP address of the server.

Initial Database

Set the initial database which user connects when making connection.

OS authentication

Use OS user login credentials to authenticate database users.

Password

Password for connecting to the database server.

Port

A TCP/IP port for connecting to the database server.

Role

Indicate that the database user is connecting with either the Default, SYSOPER or SYSDBA system privilege.

Type

Existing Database File	Connect to an existing database in the Database File .
New SQLite 3	Create a new SQLite 3 database in the Database File .
New SQLite 2	Create a new SQLite 2 database in the Database File .

User Name

User name for connecting to the database server.

MongoDB

To successfully establish a new connection to local/remote server - no matter via SSL or SSH, set the database login information in the General tab. If your Internet Service Provider (ISP) does not provide direct access to its server, Secure Tunneling Protocol (SSH) is another solution.

Connection Name

Enter a friendly name to best describe your connection.

Add To

After you logged in [Navicat Cloud](#) or [On-Prem Server](#), you can choose to save the connection to My Connections or a project.

Type

The type of your MongoDB server: Standalone, Shard Cluster or Replica Set.

SRV record

Check this option to connect the server using an SRV Record.

Host

A host name, IP address, or UNIX domain socket of the server.

Port

A TCP/IP port for connecting to the server.

Member

Add or remove the members of replica set or the instances of sharded cluster to the connection.

Read Preference

Choose the replica set read preference for this connection.

Replica Set

The name of the replica set.

Authentication

Choose the authentication mechanism that MongoDB will use to authenticate the connection.

None	No authentication.
Password	Specify the Authentication Database name associated with the User Name and Password .
LDAP	Specify the User Name and Password .
Kerberos	Set the Kerberos Service Name and the user Principal . Enable Use canonicalized host name if you want the Kerberos service canonicalizes host name.
X.509	x.509 certificate authentication.

Use MongoDB URI

You can also use a MongoDB URI to connect your MongoDB server. Simply click the **URI** button and paste the URI. Navicat will automatically fill out the options in the General, SSL and SSH tabs.

Redis

To successfully establish a new connection to local/remote server - no matter via SSL or SSH, set the database login information in the General tab. If your Internet Service Provider (ISP) does not provide direct access to its server, Secure Tunneling Protocol (SSH) is another solution.

Connection Name

Enter a friendly name to best describe your connection.

Add To

After you logged in [Navicat Cloud](#) or [On-Prem Server](#), you can choose to save the connection to My Connections or a project.

Type

The type of your Redis server: Standalone, Cluster or Sentinel.

Host

A host name, IP address, or UNIX domain socket of the server.

Port

A TCP/IP port for connecting to the server.

Authentication

Choose the authentication mechanism that Redis will use to authenticate the connection.

None	No authentication.
Password	Enter the Password if the Redis server is password protected via the requirepass option.
Username & Password	Enter the User Name and Password if Redis ACLs are used.

Advanced Settings

Note: The following options depend on the connection server type and sort in ascending order.

Auto connect

Open the connection at application startup automatically.

Cipher Name

Choose the encryption algorithm when connecting to an encrypted SQLite database.

Client Character Set

Choose the session client character set used in Navicat.

Client Driver Version

Choose the client driver used to connect the server. If the default driver does not work, you can change this setting to Legacy.

Compatibility

Enable the Compatibility tab for setting the compatibility mode for MySQL connection.

Connection Timeout

Specify the amount of time to wait for a connection to be established before timing out.

Encoding

Choose a codepage for converting data to display in Navicat UI.

Encrypt

Enable this option and provide **Password** when connecting to an encrypted SQLite database.

Execution Timeout

Specify the amount of time to wait before execution of a task is completed on the server.

Initial Queries

Specify the initial query commands to be executed when connecting to the server.

Keepalive interval

Keep the connection with the server alive by pinging it. You can set the period between pings in the edit box.

Limit connection sessions

Specify the maximum number of concurrent connections that the server allows.

Read Timeout

Specify the amount of time to wait for more data from a connection before aborting the read.

Retryable Reads

Disable this option to specify "retryReads=false" in the connection string.

Retryable Writes

Disable this option to specify "retryWrites=false" in the connection string.

Server Selection Timeout

Specify the amount of time to block for server selection before throwing an exception.

Settings Location

When a new connection is being established, Navicat will create a subfolder under the Settings Location. Most files are stored within this subfolder:

File in Settings Location	Server Type	File Extension
Backup	MySQL, PostgreSQL, SQLite and MariaDB	.nb3
	Redis	.nbr
Backup Profile	MySQL	.nbakmysql
	PostgreSQL	.nbakpgsql
	SQLite	.nbaksqlite
	SQL Server	.nbakmssql
	MariaDB	.nbakmariadb
	Redis	.nbakredis
Data Pump Export Profile	Oracle	.nbakora
Data View Profile	Redis	.ndvredis
ER Diagram File	MySQL, Oracle, PostgreSQL, SQLite, SQL Server and MariaDB	.nmodel
Export Materialized View Profile	Oracle	.nexpmora
	PostgreSQL	.nexpmpgsql

Export Query Result Profile	MySQL	.nexpqmysql
	Oracle	.nexpqora
	PostgreSQL	.nexpqpgsql
	SQLite	.nexpqsqlite
	SQL Server	.nexpqmssql
	MariaDB	.nexpqmariadb
	MongoDB	.nexpqmongodb
Export Table/Collection Profile	MySQL	.nexptmysql
	Oracle	.nexptora
	PostgreSQL	.nexptpgsql
	SQLite	.nexptsqlite
	SQL Server	.nexptmssql
	MariaDB	.nexptmariadb
	MongoDB	.nexptmongodb
Export View Result Profile	MySQL	.nexpvmysql
	Oracle	.nexpvora
	PostgreSQL	.nexpvpgsql
	SQLite	.nexpvsqlite
	SQL Server	.nexpvmssql
	MariaDB	.nexpvmariadb
	MongoDB	.nexpvmongodb
Import Table/Collection Profile	MySQL	.nimpmysql
	Oracle	.nimpora
	PostgreSQL	.nimpppgsql
	SQLite	.nimpsqlite
	SQL Server	.nimpmssql
	MariaDB	.nimpmariadb
	MongoDB	.nimpmongodb
MapReduce	MongoDB	.mapreduce
Pub/Sub	Redis	.npsbredis
Pub/Sub Archive File	Redis	.nrpsbmlog
Query	MySQL, Oracle, PostgreSQL, SQLite, SQL Server and MariaDB	.sql
	MongoDB	.js
	Redis	.redis
Schema Analysis	MongoDB	.nsatmongodb

Socket Timeout

Specify the amount of time to wait for an inactive socket before closing it.

TDS Version

Choose the TDS protocol version supported by your server if the connection runs into an incompatibility.

Trust Server Certificate

Skip the step that validates the server certificate. The server certificate is automatically trusted.

Use compression

Use compression protocol. It is used if both client and server support zlib compression, and the client requests compression.

Use socket file

Use socket file for localhost connection.

Write Timeout

Specify the amount of time to wait for a block to be written to a connection before aborting the write.

Databases Settings

MySQL, Oracle, PostgreSQL, SQL Server, MariaDB, MongoDB, Redis

In the **Databases** tab, you can set which databases will be shown in the Navigation pane when connecting to your server. It is not obligatory. To start working with custom database settings, check **Use custom database list**. Then, check the preferable databases in the **Name** column. If you want Navicat automatically open the databases at connection, check the **Auto Open** box.

Add a hidden database to the list

1. Click the **+** button.
2. Enter the database name.
3. Check the newly added database in the database list.

Remove a database from the list

1. Select the database in the database list.
2. Click the **-** button.

Note: The database will be just removed from the database list box, it will still exist in the server.

SQLite

In the **Databases** tab, you can attach SQLite database files to the connection. Click the **+** button and enter the information:

Option	Description
Database Name	Enter the database name which displays in Navicat.
Database File	Choose the file path of a database file.
Encrypt	Check this option and provide the Password if the database file is encrypted.

To detach a database, select it from the list and click the - button.

SSL Settings

Secure Sockets Layer(SSL) is a protocol for transmitting private documents via the Internet. To get a secure connection, the first thing you need to do is to install OpenSSL Library and download Database Source.

Note: Available only for MySQL, PostgreSQL, MariaDB, MongoDB and Redis. Support from PostgreSQL 8.4 or later.

MySQL and MariaDB Connections

To provide authentication details, enable **Use authentication** and fill in the required information:

Client Key

The SSL key file in PEM format to use for establishing a secure connection.

Client Certificate

The SSL certificate file in PEM format to use for establishing a secure connection.

CA Certificate

The path to a file in PEM format that contains a list of trusted SSL certificate authorities.

Verify server certificate against CA

Check the server's Common Name value in the certificate that the server sends to the client.

Specified Cipher

A list of permissible ciphers to use for SSL encryption.

PostgreSQL Connection

Choose the **SSL Mode**:

allow	First try a non-SSL connection; if that fails, try an SSL connection.
prefer	First try an SSL connection; if that fails, try a non-SSL connection.
require	Only try an SSL connection.
verify-ca	Only try an SSL connection, and verify that the server certificate is issued by a trusted CA.
verify-full	Only try an SSL connection, verify that the server certificate is issued by a

	trusted CA and that the server hostname matches that in the certificate.
--	--

To provide authentication details, enable **Use authentication** and fill in the required information:

Client Key

The path of the client private key.

Client Certificate

The path of the client certificate.

Root Certificate

The path of the trusted certificate authorities.

Certificate Revocation List

The file path of the SSL certificate revocation list (CRL).

MongoDB Connection

To provide authentication details, enable **Use authentication** and fill in the required information:

Client Key

The SSL key file in PEM format to use for establishing a secure connection.

Client Key Password

The password of the key file.

Allow any server SSL certificates

Check this option if your MongoDB server allows any server SSL certificates.

CA Certificate

The path to a file in PEM format that contains a list of trusted SSL certificate authorities.

Certificate Revocation List

The file path of the SSL certificate revocation list (CRL).

Allow invalid host names

Check this option to allow invalid hostnames in SSL certificates.

Redis Connection

To provide authentication details, enable **Use authentication** and fill in the required information:

Client Key

The SSL key file in PEM format to use for establishing a secure connection.

Client Key Password

The password of the key file.

Allow any server SSL certificates

Check this option if your Redis server allows any server SSL certificates.

CA Certificate

The path to a file in PEM format that contains a list of trusted SSL certificate authorities.

Server Name Indication

The Server Name Indication (SNI) value used when establishing the SSL connection to the Redis server.

SSH Settings

Secure SHell (SSH) is a program to log in into another computer over a network, execute commands on a remote server, and move files from one machine to another. It provides strong authentication and secure encrypted communications between two hosts, known as **SSH Port Forwarding (Tunneling)**, over an insecure network. Typically, it is employed as an encrypted version of Telnet.

In a Telnet session, all communications, including username and password, are transmitted in plain-text, allowing anyone to listen-in on your session and steal passwords and other information. Such sessions are also susceptible to session hijacking, where a malicious user takes over your session once you have authenticated. SSH serves to prevent such vulnerabilities and allows you to access a remote server's shell without compromising security.

Note: Available only for MySQL, Oracle, PostgreSQL, SQL Server, MariaDB, MongoDB and Redis.

Please make sure that the parameter - "AllowTcpForwarding" in the Linux server must be set to value "yes", otherwise, the SSH port forwarding will be disabled. To look for the path: /etc/ssh/sshd_config. By default, the SSH port forwarding should be enabled. Please double check the value settings.

Even the server support SSH tunnel, however, if the port forwarding being disabled, Navicat cannot connect via SSH Port 22.

Host

A host where SSH server is activated.

Note: The host name in the General tab should be set relatively to the SSH server which provided by your database hosting company.

Port

A port where SSH server is activated, by default it is 22.

User Name

A user on SSH server machine. (It is not a user of database server.)

Authentication Method

Password	Provide the SSH server user Password .
Public Key	Private Key It is used together with your public key. The private key should be readable only by you. Passphrase A passphrase is exactly like a password, except that it applies to the keys you are generating and not an account.

Use compression

Request compression of all data (including stdin, stdout, stderr, and data for forwarded X11 and TCP connections). The compression algorithm is the same used by gzip(1), and the "level" can be controlled by the CompressionLevel option for protocol version 1.

Note: HTTP Tunnel and SSH Tunnel cannot be function simultaneously. The SSH Tunnel is disabled when you select the HTTP Tunnel and vice versa.

HTTP Settings

HTTP Tunneling is a method for connecting to a server that uses the same protocol (http://) and the same port (port 80) as a web server does. It is used while your ISPs do not allow direct connections, but allows establishing HTTP connections.

Note: Available only for MySQL, PostgreSQL, SQLite and MariaDB.

Uploading the Tunneling Script

To use this connection method, first thing you need to do is to upload the tunneling script to the web server where your server is located.

Note: Click the **Export Tunnel Script** button to extract the script file, **ntunnel_mysql.php** (for both MySQL and MariaDB), **ntunnel_pgsql.php** or **ntunnel_sqlite.php**.

Setting up HTTP Tunnel

The following instruction guides you through the process of configuring a HTTP connection.

1. Select the HTTP tab and enable **Use HTTP tunnel**.

2. Enter URL of the tunneling script.
e.g. `http://www.navicat.com/ntunnel_mysql.php`
3. If the tunneling script is hosted in a password protected server, you can provide the required authentication details.
4. If your server installed a Web Application Firewall, you can check the **Encode outgoing query with base64** option.
5. If you have to access internet over a proxy server, click the **Proxy Settings** button and provide the details.

Note: HTTP Tunnel and SSH Tunnel cannot be function simultaneously. The SSH Tunnel is disabled when you select the HTTP Tunnel and vice versa.

Compatibility Settings

If your server is a variant of MySQL or has proxy middleware installed, you can enable compatibility mode and set the corresponding settings for the connection.

Note: Available only for MySQL.

Force lower_case_table_names as

Set the value of the lower_case_table_name system variable.

Force sql_mode as

Set the value of the sql_mode system variable.

Force NDB cluster support as

Include or exclude the support for the NDBCLUSTER storage engine.

Force database listing method as

Use the SHOW DATABASES statement to retrieve the information for listing databases, or select the information from the INFORMATION_SCHEMA database.



Force view listing method as

Use the SHOW FULL TABLES statement to retrieve the information for listing tables, or select the information from the INFORMATION_SCHEMA database.

Connect with Different Profiles

You can have multiple profiles for each connection, with slightly different connection settings. For example, different database users.

Create Connection Profile


1. In the connection window, click .
2. Click .
3. Enter the name of the profile.
4. Enter the connection settings.
5. Click **OK**.

Switch Profile

1. In the main window, control-click a connection and select **Switch Connection Profile**.
2. Select the profile name.


Hint: You can also set the default active profile in the connection window.

Manage Connections


The Manage Connections feature is a centralized way to manage connections in My Connections or projects. To open the manager, you can hover over **My Connections** or a project and click .

Note: Changes made in the Manage Connection window will be immediately applied to the Navigation pane.

Create Connection


1. In the Manage Connections window, click .
2. In the New Connection window, select your server type and click **Next**.
3. Enter the necessary information.
4. Click **OK**.

Edit Connection Settings


1. In the Manage Connections window, select your connection.
2. Click .
3. In the Edit Connection window, modify your connection information.
4. Click **OK**.

Hint: You can view / copy your Navicat URI or MongoDB URI by clicking **URI**.


Star / Unstar Connections

1. In the Manage Connections window, select the connections you want to add or remove stars.
2. Click .

Hide / Unhide Connections

1. In the Manage Connections window, select the connections you want to hide or unhide.
2. Click .

Delete Connections

1. In the Manage Connections window, select the connections you want to delete.
2. Click .
3. Click **Delete**.

Search Connection Information

Navicat allows you to quickly search for specific connection information within the application. It helps you locate specific connections by searching for keywords related to the connection details. You can search for connection information such as connection names, host names, IP addresses, port numbers and other relevant settings.

In the Manage Connections window, simply enter the search string in the **Search connection info** box. As you type, search results automatically update and all matching text strings are highlighted.

Chapter 5 - Server Objects

About Server Objects

Navicat provides powerful tools to manage server objects, such as databases, tables, views, functions, etc.

Some server objects may have been hidden by Navicat. These objects include system databases, system tables and so on. To show the hidden items, choose **View -> Show Hidden Items** from the menu bar.

Note: Before working with the server objects in Navicat, you should establish the connection first.

In object designers, you can preview the necessary SQL statements, scripts or commands for creating or editing the object on the **SQL Preview**, **Script Preview** or **Command Preview** tab. For some database or schema objects, you can use the bottom drop-down menu to show the SQL, scripts or commands which will be run when choosing **Save** or **Save As** from the **File** menu.

MySQL / MariaDB

Databases

To start working with the server objects, you should create and open a connection. If the server is empty, you need to create a new database.

Create a new database


1. In the Navigation pane, control-click a connection and select **New Database**.
2. Enter the database properties in the pop-up window.

Edit an existing database

1. In the Navigation pane, control-click a database and select **Edit Database**.
2. Edit the database properties in the pop-up window.

Note: MySQL does not support renaming database through its interface at this moment. Access the directory in which databases being stored. By default, all databases store within a directory called data under MySQL Installation folder. For example: /usr/local/mysql5/data. You must stop MySQL before you can rename the database.

Tables

Tables are database objects that contain all data in a database. A table is a set of rows and columns, and their intersections are fields. In the main window, click  **Table** to open the table object list.

There are two ways to open a table with graphical fields, control-click a table and select:

Option	Description
--------	-------------

Open Table	Navicat loads all your BLOB fields (images) while opening the table.
Open Table (Quick)	Faster performance for opening the graphical table, as BLOB fields (images) will not be loaded until you click on the cell. (It is invisible by default until you hold down the OPTION key when choosing the pop-up menu.)

You can create a table shortcut by dragging the table out. It provides a convenient way for you to open your table for entering data directly without activating the Navicat main window.

To empty a table, control-click the selected table and select **Empty Table** from the pop-up menu. This option is only applied when you wish to clear all the existing records without resetting the auto-increment value. To reset the auto-increment value while emptying your table, use **Truncate Table**.

Table Designer

Table Designer is the basic Navicat tool for working with tables. It allows you to create, edit and drop table's fields, indexes, foreign keys, and much more.

In the **Fields** tab, you can search a field name by choosing **Edit -> Find -> Find** or pressing COMMAND-F. You can change the order of a field, simply drag and drop it to the desired location.


Note: The tabs and options in the designer depend on the server type and version.

Table Viewer

When you open a table, **Table Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Note: Transaction is only available for INNODB tables.



Views




A view allows users to access a set of tables as if it is a single table. You can use views to restrict access to rows. In the main window, click  **View** to open the view object list.

You can create a view shortcut by dragging the view out. It provides a convenient way for you to open your view without activating the Navicat main window.

View Designer

View Designer is the basic Navicat tool for working with views. You can edit the view definition as SQL statement (SELECT statement it implements) in the **SQL Editor** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details. If you want to load SQL statement from a SQL file to the editor, you can choose **File -> Import SQL**.

Button	Description
	Preview the data of the view.
	Show the Query Plan of the view.


	Stop the preview process.
	Build the view visually. It allows you to create and edit views without knowledge of SQL. See Query Builder for details.
	Format the codes with the Beautify SQL settings in Editor.

View Viewer


When you open a view, **View Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Note: Transaction is only available for updatable views.

Procedures / Functions

Procedures and functions (stored routines) are supported in MySQL 5.0. A stored routine is a set of SQL statements that can be stored in the server. In the main window, click  **Function** to open the function object list.

Function Wizard

Click  from the object toolbar. **Function Wizard** will pop up and it allows you to create a procedure/function easily.


1. Select the type of the routine: **Procedure** or **Function**.
2. Define the parameters. Set the **Mode**, **Name** and/or **Type** under the corresponding columns.
3. If you create a function, select the **Return Type**.
4. Select the additional function options.

Hint: Once click the **Skip** button, you can go to [Settings](#) to enable the function wizard.

Function Designer



Function Designer is the basic Navicat tool for working with procedures/functions. You can enter a valid SQL statement in the **Definition** tab. This can be a simple statement such as SELECT or INSERT, or it can be a compound statement written using BEGIN and END. Compound statements can contain declarations, loops, and other control structure statements. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details.

Results

To execute the procedure/function, click  on the toolbar. If the SQL statement is correct, the statement will be executed and, if the statement is supposed to return data, the **Result** tab opens with the data returned. If an error occurs while executing the procedure/function, execution stops, the appropriate error message is displayed. If the procedure/function requires input parameters, the **Input Parameters** dialog will pop up. Check the **Raw Mode** option to pass the inputted values to the procedure/function without quotation marks.

Note: Navicat supports to return 20 result sets.



Tablespaces

An InnoDB general tablespace is a shared tablespace which can hold multiple tables, and supports all table row formats. An InnoDB undo tablespace contains undo logs. In MySQL NDB Cluster, tablespace can contain one or more data files, providing storage space for NDB Cluster Disk Data table. In the main window, click  **Others** ->  **Tablespace** to open the tablespace object list.

Tablespace Designer

Tablespace Designer is the basic Navicat tool for working with tablespaces. It allows you to set the table engine, specify the data file, etc.


Events

An event is a task that run according to a schedule. In the main window, click  **Others** ->  **Event** to open the event object list.

Event Designer

Event Designer is the basic Navicat tool for working with events. You can enter a valid SQL procedure statement in the **Definition** tab. This can be a simple statement such as SELECT or INSERT, or it can be a compound statement written using BEGIN and END. Compound statements can contain declarations, loops, and other control structure statements. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details.

Other Objects

Navicat also allows you to manage other MySQL / MariaDB objects: Sequence. In the main window, click  **Others** and select an object to open the object list.

Note: Sequences are available for MariaDB 10.3 or later.

Maintain Objects

Navicat provides a complete solution for maintaining MySQL / MariaDB objects.

1. In the main window, select objects in the Navigation pane or the Objects tab.
2. Control-click the selected objects.
3. Choose **Maintain**, and then choose a maintain option the from the pop-up menu.
4. Results show in a pop-up window.

Table

Option	Description
Analyze Table	Analyze and store the key distribution for the table.
Check Table	Check the table for errors.

Optimize Table	Optimize the table to reduce storage space and improve I/O efficiency.
Repair Table	Repair the possibly corrupted table.
Get Rows Count	Count the number of rows in the table.

Tablespace

Option	Description
Set Active	Mark an InnoDB undo tablespace as active.
Set Inactive	Mark an InnoDB undo tablespace as inactive.


Oracle



Schemas

To start working with the server objects, you should create and open a connection. When you create a user account, you are also implicitly creating a schema for that user. A schema is a logical container for the database objects (such as tables, views, triggers, and so on) that the user creates. The schema name is the same as the user name, and can be used to unambiguously refer to objects owned by the user.

Hint: Oracle interprets non-quoted object identifiers as uppercase. In Navicat, all object identifiers will be quoted. That is, Navicat saves exactly what you have inputted.

Tables

Tables are database objects that contain all data in a database. A table is a set of rows and columns, and their intersections are fields. In the main window, click  **Table** to open the table object list.

You can create **Normal** / **External** / **Index Organized** tables. To create a new normal table, simply click  from the object toolbar. Or, you can click and hold the  button and choose the table type.

There are two ways to open a table with graphical fields, control-click a table and select:

Option	Description
Open Table	Navicat loads all your BLOB fields (images) while opening the table.
Open Table (Quick)	Faster performance for opening the graphical table, as BLOB fields (images) will not be loaded until you click on the cell. (It is invisible by default until you hold down the OPTION key when choosing the pop-up menu.)

You can create a table shortcut by dragging the table out. It provides a convenient way for you to open your table for entering data directly without activating the Navicat main window.

To empty a table, control-click the selected table and select **Empty Table** from the pop-up menu. This option is only applied when you wish to clear all the existing records without resetting the auto-increment value. To reset the auto-increment value while emptying your table, use **Truncate Table**.

Table Designer

Table Designer is the basic Navicat tool for working with tables. It allows you to create, edit and drop table's fields, indexes, foreign keys, and much more.


In the **Fields** tab, you can search a field name by choosing **Edit -> Find -> Find** or pressing COMMAND-F. You can change the order of a field when creating new tables, simply drag and drop it to the desired location.

Note: The tabs and options in the designer depend on the server version and the table type.

Table Viewer

When you open a table, **Table Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.






Views

A view allows users to access a set of tables as if it is a single table. You can use views to restrict access to rows. In the main window, click  **View** to open the view object list.

You can create a view shortcut by dragging the view out. It provides a convenient way for you to open your view without activating the Navicat main window.

View Designer


View Designer is the basic Navicat tool for working with views. You can edit the view definition as SQL statement (SELECT statement it implements) in the **SQL Editor** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details. If you want to load SQL statement from a SQL file to the editor, you can choose **File -> Import SQL**.

Button	Description
	Preview the data of the view.
	Show the Query Plan of the view.
	Stop the preview process.
	Build the view visually. It allows you to create and edit views without knowledge of SQL. See Query Builder for details.
	Format the codes with the Beautify SQL settings in Editor.

View Viewer

When you open a view, **View Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Materialized Views






Materialized Views are schema objects that used to summarize, compute, replicate, and distribute data. In the main window, click  **Materialized View** to open the materialized view object list.

You can create a materialized view shortcut by dragging the materialized view out. It provides a convenient way for you to open your materialized view without activating the Navicat main window.

To refresh a materialized view, control-click it in the Objects tab and select **Refresh Materialized View** from the pop-up menu.

Materialized View Designer


Materialized View Designer is the basic Navicat tool for working with materialized views. You can edit the view definition as SQL statement (SELECT statement it implements) in the **SQL Editor** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details. If you want to load SQL statement from a SQL file to the editor, you can choose **File -> Import SQL**.

Button	Description
	Preview the data of the materialized view.
	Show the Query Plan of the materialized view.
	Stop the preview process.
	Build the materialized view visually. It allows you to create and edit materialized views without knowledge of SQL. See Query Builder for details.
	Format the codes with the Beautify SQL settings in Editor.

Materialized View Viewer

When you open a materialized view, **Materialized View Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Procedures / Functions

Procedures and functions are schema objects that consist a set of SQL statements and stored in the server. In the main window, click  **Function** to open the function object list.

Function Wizard

Click  from the object toolbar. **Function Wizard** will pop up and it allows you to create a procedure/function easily.

1. Select the type of the routine: **Procedure** or **Function**.
2. Define the parameters. Set the **Mode**, **Name**, **Type Schema** and **Type** under the corresponding columns.
3. If you create a function, select the **Return Type**.
4. Select the additional function options.







Hint: Once click the **Skip** button, you can go to [Settings](#) to enable the function wizard.

Function Designer


Function Designer is the basic Navicat tool for working with procedures/functions. You can enter a valid SQL statement in the **Definition** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details.

The **Code Outline** pane displays information about the procedure/function including parameters, code body, etc. If the Code Outline pane is hidden, choose **View -> Code Outline**.

Note: Available only in Navicat Premium, Enterprise and Standard Edition.


Button	Description
	Refresh the code outline.
	Turn mouse over highlight on or off.
	Show the detail view of the code outline.
	Toggle sorting by position.
	Expand the selected item.
	Collapse the selected item.

Results

To execute the procedure/function, click  on the toolbar. If the SQL statement is correct, the statement will be executed and, if the statement is supposed to return data, the **DBMS Output** tab opens with the data returned. If an error occurs while executing the procedure/function, execution stops, the appropriate error message is displayed. If the procedure/function requires input parameters, the **Input Parameters** dialog will pop up. Check the **Raw Mode** option to pass the inputted values to the procedure/function without quotation marks.



Note: Navicat supports to return 20 result sets.

Debug (Available only in Navicat Premium, Enterprise and Standard Edition)


You can add/remove breakpoints for debugging by clicking  in the grey area beside each statement.


Click  on the toolbar to launch the [Oracle Debugger](#). Enter the input parameters if necessary.

Packages

Packages are encapsulated collections of related procedures, stored functions, and other program objects stored together in the database. A package consists of two parts: a specification and a body. In the main window, click  **Others ->  Package** to open the package object list.

Package Designer & Package Body Designer







Package Designer and **Package Body Designer** are the basic Navicat tools for working with packages. After saving the package in Package Designer, you can edit its package body by clicking .

Likewise, you can edit its package specification by clicking  in Package Body Designer.


You can enter a valid SQL statement in the **Definition** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details.

The **Code Outline** pane displays information about the package/package body including function, procedure, parameter, code body, etc. If the Code Outline pane is hidden, choose **View -> Code Outline**.


Note: Available only in Navicat Premium, Enterprise and Standard Edition.



Button	Description
	Refresh the code outline.
	Turn mouse over highlight on or off.
	Show the detail view of the code outline.
	Toggle sorting by position.
	Expand the selected item.
	Collapse the selected item.

Results



To execute the package, click  on the toolbar. If the SQL statement is correct, the statement will be executed and, if the statement is supposed to return data, the **DBMS Output** tab opens with the data returned. If an error occurs while executing the package, execution stops, the appropriate error message is displayed. If the package requires input parameters, the **Input Parameters** dialog will pop up.

Debug (Available only in Navicat Premium, Enterprise and Standard Edition)


You can add/remove breakpoints for debugging by clicking  in the grey area beside each statement.

Before debugging, click  to save and compile the package. Then, click  on the toolbar to launch the [Oracle Debugger](#). Enter the input parameters if necessary.


Recycle Bin

Recycle bin contains dropped tables and any associated objects such as indexes, constraints, nested tables. In the main window, click  **Others** ->  **Recycle Bin** to open the recycle bin object list.

Restore a table

1. Select a table in the Objects tab.
2. Click .

Remove an object

1. Select an object for purging in the Objects tab.
2. Click .
3. Confirm deleting in the dialog window.


Remove all objects

1. Control-click anywhere in the Objects tab and select **Purge Recycle Bin** from the pop-up menu.
2. Confirm deleting in the dialog window.

Remove all objects of any users

1. Log in a user with SYSDBA privilege.
2. Control-click anywhere in the Objects tab and select **Purge DBA Recycle Bin** from the pop-up menu.
3. Confirm deleting in the dialog window.

Other Objects

Navicat also allows you to manage other Oracle objects: Database Link, Index, Java, Materialized View Log, Sequence, Synonym, Trigger, Type, XML Schema, Directory, Public Database Link, Public Synonym and Tablespace. In the main window, click  **Others** and select an object to open the object list.

Maintain Objects

Navicat provides a complete solution for maintaining Oracle objects.

1. In the main window, select objects in the Navigation pane or the Objects tab.
2. Control-click the selected objects.
3. Choose **Maintain**, and then choose a maintain option the from the pop-up menu.
4. Results show in a pop-up window.

Table

Option	Description
Enable Table Lock	Allow DDL operations on the table.
Disable Table Lock	Prevent DDL operations on the table.
Enable Row Movement	Allow the database to move a row, thus changing the rowid.
Disable Row Movement	Prevent the database from moving a row, thus preventing a change of rowid.
Shrink Space	Shrink space in the table.
Move	Relocate data of the table.
Validate Table Structure	Verify the integrity of the structure of the table.
Collect Table Statistics	Analyze the contents of the table.

View

Option	Description
--------	-------------

Compile	Recompile the view specification or body.
---------	---

Procedure / Function

Option	Description
Compile	Recompile the specification or body.
Compile for Debug	Recompile the specification or body. Instruct the PL/SQL compiler to generate and store the code for use by the debugger.

Index

Option	Description
Rebuild Index	Re-create the index or one of its partitions or subpartitions.
Make Index Unusable	Make the index unusable.
Coalesce Index	Merge the contents of index blocks where possible to free blocks for reuse.
Compute Index Statistics	Compute the statistics of the index.

Java

Option	Description
Compile or Resolve	Resolve the primary Java class schema object.
Set AuthID Current User	Set the invoker rights to AUTHID CURRENT_USER.
Set AuthID Definer	Set the invoker rights to AUTHID DEFINER.

Materialized View

Option	Description
Enable Row Movement	Allow the database to move a row, thus changing the rowid.
Disable Row Movement	Prevent the database from moving a row, thus preventing a change of rowid.
Shrink Space	Compact the materialized view segment.
Compile	Revalidate the materialized view.
Force Refresh	Refresh the materialized view.

Materialized View Log

Option	Description
Enable Row Movement	Allow the database to move a row, thus changing the rowid.
Disable Row Movement	Prevent the database from moving a row, thus preventing a change of rowid.
Shrink Space	Compact the materialized view log segments.

Package

Option	Description
Compile	Recompile the package specification and body.
Compile for Debug	Recompile the package specification and body. Instruct the PL/SQL

	compiler to generate and store the code for use by the debugger.
--	--

Trigger

Option	Description
Compile	Recompile the trigger.
Compile for Debug	Recompile the trigger. Instruct the PL/SQL compiler to generate and store the code for use by the debugger.
Enable Trigger	Enable the trigger.
Disable Trigger	Disable the trigger.

Type

Option	Description
Compile	Recompile the type specification and body.
Compile for Debug	Recompile the type specification and body. Instruct the PL/SQL compiler to generate and store the code for use by the debugger.

XML Schema

Option	Description
Compile	Recompile the already registered XML schema.
Purge XML Schema	Removes the XML schema completely from Oracle XML DB.

Tablespace

Option	Description
Read Only	Place the tablespace in transition read-only mode.
Read Write	Allow write operations on a previously read-only tablespace.
Online	Take the tablespace online.
Offline	Take the tablespace offline.
Coalesce	Combine all contiguous free extents into larger contiguous extents for each datafile in the tablespace.
Shrink Space	Reduce the amount of space the tablespace is taking.

PostgreSQL

Databases & Schemas

To start working with the server objects, you should create and open a connection. If the server is empty, you need to create a new database and/or a new schema.

Create a new database

1. In the Navigation pane, control-click a connection and select **New Database**.
2. Enter the database properties in the pop-up window.

Edit an existing database

1. In the Navigation pane, control-click a database and select **Edit Database**.
2. Edit the database properties in the pop-up window.


Create a new schema



1. In the Navigation pane, control-click a database and select **New Schema**.
2. Enter the schema properties in the pop-up window.

Edit an existing schema

1. In the Navigation pane, control-click a schema and select **Edit Schema**.
2. Edit the schema properties in the pop-up window.

Tables

Tables are database objects that contain all data in a database. A table is a set of rows and columns, and their intersections are fields. In the main window, click  **Table** to open the table object list.

You can create **Normal** / **Foreign** / **Partitioned** tables. To create a new normal table, simply click  from the object toolbar. Or, you can click and hold the  button and choose the table type.

There are two ways to open a table with graphical fields, control-click a table and select:

Option	Description
Open Table	Navicat loads all your BLOB fields (images) while opening the table.
Open Table (Quick)	Faster performance for opening the graphical table, as BLOB fields (images) will not be loaded until you click on the cell. (It is invisible by default until you hold down the OPTION key when choosing the pop-up menu.)

You can create a table shortcut by dragging the table out. It provides a convenient way for you to open your table for entering data directly without activating the Navicat main window.

To empty a table, control-click the selected table and select **Empty Table** from the pop-up menu. This option is only applied when you wish to clear all the existing records without resetting the auto-increment value. To reset the auto-increment value while emptying your table, use **Truncate Table**.

Table Designer

Table Designer is the basic Navicat tool for working with tables. It allows you to create, edit and drop table's fields, indexes, foreign keys, and much more.


In the **Fields** tab, you can search a field name by choosing **Edit** -> **Find** -> **Find** or pressing COMMAND-F.

Note: The tabs and options in the designer depend on the server version and the table type.

Table Viewer

When you open a table, **Table Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.






Views

A view allows users to access a set of tables as if it is a single table. You can use views to restrict access to rows. In the main window, click  **View** to open the view object list.

You can create a view shortcut by dragging the view out. It provides a convenient way for you to open your view without activating the Navicat main window.

View Designer


View Designer is the basic Navicat tool for working with views. You can edit the view definition as SQL statement (SELECT statement it implements) in the **SQL Editor** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details. If you want to load SQL statement from a SQL file to the editor, you can choose **File -> Import SQL**.

Button	Description
	Preview the data of the view.
	Show the Query Plan of the view.
	Stop the preview process.
	Build the view visually. It allows you to create and edit views without knowledge of SQL. See Query Builder for details.
	Format the codes with the Beautify SQL settings in Editor.

View Viewer

When you open a view, **View Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Materialized Views

Materialized Views are schema objects that used to summarize, compute, replicate, and distribute data. In the main window, click  **Materialized View** to open the materialized view object list.






You can create a materialized view shortcut by dragging the materialized view out. It provides a convenient way for you to open your materialized view without activating the Navicat main window.

To refresh and completely replace the contents of a materialized view, control-click it in the Objects tab and select **Refresh Materialized View With -> Data** or **No Data** from the pop-up menu.

Materialized View Designer

Materialized View Designer is the basic Navicat tool for working with materialized views. You can edit the view definition as SQL statement (SELECT statement it implements) in the **SQL Editor** tab. To customize the view of the


editor and find out more features for SQL editing, see [Query Editor](#) for details. If you want to load SQL statement from a SQL file to the editor, you can choose **File -> Import SQL**.

Button	Description
	Preview the data of the materialized view.
	Show the Query Plan of the materialized view.
	Stop the preview process.
	Build the materialized view visually. It allows you to create and edit materialized views without knowledge of SQL. See Query Builder for details.
	Format the codes with the Beautify SQL settings in Editor.


Materialized View Viewer

When you open a materialized view, **Materialized View Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Procedures / Functions

Procedures and functions are schema objects that consist a set of SQL statements and stored in the server. Procedures are supported in PostgreSQL 11. In the main window, click  **Function** to open the function object list.

Function Wizard

Click  from the object toolbar. **Function Wizard** will pop up and it allows you to create a procedure/function easily.


1. Select the type of the routine: **Procedure** or **Function**.
2. Define the parameters. Set the **Mode**, **Name**, **Type Schema**, **Type** and **Default Value** under the corresponding columns.
3. If you create a function, select the **Return Type**.
4. Select the additional function options.

Hint: Once click the **Skip** button, you can go to [Settings](#) to enable the function wizard.

Function Designer

Function Designer is the basic Navicat tool for working with procedures/functions. You can enter a valid SQL statement in the **Definition** tab. This can be a simple statement such as SELECT or INSERT, or it can be a compound statement written using BEGIN and END. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details.

Results


To execute the procedure/function, click  on the toolbar. If the SQL statement is correct, the statement will be executed and, if the statement is supposed to return data, the **Result** tab opens with the data returned. If an error occurs while executing the procedure/function, execution stops, the appropriate error message is displayed. If the

procedure/function requires input parameters, the **Input Parameters** dialog will pop up. Check the **Raw Mode** option to pass the inputted values to the procedure/function without quotation marks.

Note: Navicat supports to return 20 result sets.



Debug (Available only in Navicat Premium, Enterprise and Standard Edition)



Before debugging PL/pgSQL procedures/functions, you need to install the pldbgapi extension or enable the debugger plugin manually in the server.

Then, open a PL/pgSQL procedure/function. You can add/remove breakpoints for debugging by clicking  in the grey area beside each statement.

Click  on the toolbar to launch the [PostgreSQL Debugger](#). Enter the input parameters if necessary.

Types

Types register new data types for use in the current database. In the main window, click  **Others** ->  **Type** to open the type object list.


You can create **Base** / **Composite** / **Enum** / **Range** types. To create a new base type, simply click  from the object toolbar. Or, you can click and hold the  button and choose the type.

Type Designer

Type Designer is the basic Navicat tool for working with types. It allows you to create or edit a type.

Note: The tabs and options in the designer depend on the server version and the type you are chosen.

Foreign Servers


A foreign server typically encapsulates connection information that a foreign-data wrapper uses to access an external data resource. In the main window, click  **Others** ->  **Foreign Server** to open the foreign server object list.

To install the postgres_fdw extension for accessing data stored in external PostgreSQL servers, you can control-click anywhere in the foreign server object list and select **Install postgres_fdw Extension**.

Foreign Server Designer

Foreign Server Designer is the basic Navicat tool for working with foreign servers. It allows you to create or edit a foreign server.

Other Objects

Navicat also allows you to manage other PostgreSQL objects: Aggregate, Conversion, Domain, Index, Operator, Operator Class, Sequence, Trigger, Tablespace, Cast and Language. In the main window, click  **Others** and select an object to open the object list.

Maintain Objects

Navicat provides a complete solution for maintaining PostgreSQL objects.

1. In the main window, select objects in the Navigation pane or the Objects tab.
2. Control-click the selected objects.
3. Choose **Maintain**, and then choose a maintain option the from the pop-up menu.
4. Results show in a pop-up window.

Database

Option	Description
Allow	Users can connect to the database.
Disallow	No users can connect to the database.
Analyze Database	Collect statistics about the database.
Vacuum Database	Garbage-collect and optionally analyze the database.
Reindex Database	Recreate all indexes within the database.

Table

Option	Description
Analyze Table	Collect statistics about the contents of the table.
Vacuum Table	Garbage-collect and optionally analyze the table.
Reindex Table	Recreate all indexes of the table.

Manage Extensions

PostgreSQL has various extensions, supplying extra functions, operators, or types to extend the functionality of a database. You can install the extensions that are supported by your PostgreSQL server.

Install an extension

1. In the Navigation pane, control-click a database and select **Manage Extensions**.
2. All available extensions are listed on the left. Move an available extension to the Installed list.
3. Click **OK**.

Remove an extension

1. In the Navigation pane, control-click a database and select **Manage Extensions**.
2. Move an installed extension to the Available list.
3. Click **OK**.

SQL Server

Databases & Schemas

To start working with the server objects, you should create and open a connection. If the server is empty, you need to create a new database and/or a new schema.

Create a new database

1. In the Navigation pane, control-click a connection and select **New Database**.
2. Enter the database properties in the pop-up window.

Edit an existing database

1. In the Navigation pane, control-click a database and select **Edit Database**.
2. Edit the database properties in the pop-up window.


Create a new schema

1. In the Navigation pane, control-click a database and select **New Schema**.
2. Enter the schema properties in the pop-up window.

Edit an existing schema

1. In the Navigation pane, control-click a schema and select **Edit Schema**.
2. Edit the schema properties in the pop-up window.

Tables

Tables are database objects that contain all data in a database. A table is a set of rows and columns, and their intersections are fields. In the main window, click  **Table** to open the table object list.

There are two ways to open a table with graphical fields, control-click a table and select:

Option	Description
Open Table	Navicat loads all your BLOB fields (images) while opening the table.
Open Table (Quick)	Faster performance for opening the graphical table, as BLOB fields (images) will not be loaded until you click on the cell. (It is invisible by default until you hold down the OPTION key when choosing the pop-up menu.)

You can create a table shortcut by dragging the table out. It provides a convenient way for you to open your table for entering data directly without activating the Navicat main window.

To empty a table, control-click the selected table and select **Empty Table** from the pop-up menu. This option is only applied when you wish to clear all the existing records without resetting the auto-increment value. To reset the auto-increment value while emptying your table, use **Truncate Table**.

Table Designer

Table Designer is the basic Navicat tool for working with tables. It allows you to create, edit and drop table's fields, indexes, foreign keys, and much more.


In the **Fields** tab, you can search a field name by choosing **Edit -> Find -> Find** or pressing COMMAND-F. When creating a new table, you are allowed to insert fields or rearrange the order of the fields.

Note: The tabs and options in the designer depend on the server version.

Table Viewer

When you open a table, **Table Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.






Views

A view allows users to access a set of tables as if it is a single table. You can use views to restrict access to rows. In the main window, click  **View** to open the view object list.

You can create a view shortcut by dragging the view out. It provides a convenient way for you to open your view without activating the Navicat main window.

View Designer


View Designer is the basic Navicat tool for working with views. You can edit the view definition as SQL statement (SELECT statement it implements) in the **SQL Editor** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details. If you want to load SQL statement from a SQL file to the editor, you can choose **File -> Import SQL**.

Button	Description
	Preview the data of the view.
	Show the Query Plan of the view.
	Stop the preview process.
	Build the view visually. It allows you to create and edit views without knowledge of SQL. See Query Builder for details.
	Format the codes with the Beautify SQL settings in Editor.

View Viewer

When you open a view, **View Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Procedures / Functions

Procedures and functions are schema objects that consist a set of SQL statements and stored in the server. In the main window, click  **Function** to open the function object list.

Function Wizard

Click  from the object toolbar. **Function Wizard** will pop up and it allows you to create a procedure/function easily.

1. Select the type of the routine: **Procedure** or **Function**.
2. Define the parameters. Set the **Name**, **Type Schema**, **Type**, **Default Value**, **Output** and **Read Only** under the corresponding columns.
3. If you create a function, select the **Return Type**.
4. Select the additional function options.







Hint: Once click the **Skip** button, you can go to [Settings](#) to enable the function wizard.

Function Designer


Function Designer is the basic Navicat tool for working with procedures/functions. You can enter a valid SQL statement in the **Definition** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details.

The **Code Outline** pane displays information about the procedure/function including parameters, code body, etc. If the Code Outline pane is hidden, choose **View -> Code Outline**.

Note: Available only in Navicat Premium, Enterprise and Standard Edition.


Button	Description
	Refresh the code outline.
	Turn mouse over highlight on or off.
	Show the detail view of the code outline.
	Toggle sorting by position.
	Expand the selected item.
	Collapse the selected item.

Results

To execute the procedure/function, click  on the toolbar. If the SQL statement is correct, the statement will be executed and, if the statement is supposed to return data, the **Result** tab opens with the data returned. If an error occurs while executing the procedure/function, execution stops, the appropriate error message is displayed. If the procedure/function requires input parameters, the **Input Parameters** dialog will pop up. Check the **Raw Mode** option to pass the inputted values to the procedure/function without quotation marks.

Note: Navicat supports to return 20 result sets.

Other Objects

Navicat also allows you to manage other SQL Server objects: Index, Synonym, Trigger, Backup Device, Linked Server, Server Trigger, Assembly, Database Trigger, Partition Function and Partition Scheme. In the main window, click  **Others** and select an object to open the object list.

Maintain Objects

Navicat provides a complete solution for maintaining SQL Server objects.

1. In the main window, select objects in the Navigation pane or the Objects tab.
2. Control-click the selected objects.
3. Choose **Maintain**, and then choose a maintain option the from the pop-up menu.
4. Results show in a pop-up window.

Database

Option	Description
Read Write	Set the database to Read and Write mode.
Read Only	Set the database to Read Only mode.
Online	Bring the database online.
Offline	Take the database offline.
Emergency	Set the database to the Emergency state.
Multi User	Set the database to Multi User mode.
Single User	Set the database to Single User mode.
Restricted User	Set the database to Restricted User mode.

Assembly

Option	Description
Set Invisible	Set the assembly to not visible.
Set Visible	Set the assembly to visible.

Index

Option	Description
Rebuild Index	Rebuild and enable the index.
Reorganize Index	Reorganize the enabled index.
Disable Index	Disable the index.

Trigger / Database Trigger / Server Trigger

Option	Description
Enable Trigger	Enable the trigger.
Disable Trigger	Disable the trigger.

SQLite

Databases

To start working with the server objects, you should create and open a connection. The database file set in the General tab of the Connection window is named as the **main** database.

Attach a database file

1. In the Navigation pane, control-click a connection and select **Attach Database**.
2. Enter the database properties in the pop-up window.

Detach a database

1. In the Navigation pane, control-click an attached database and select **Detach Database**.

Encrypt main database

1. In the Navigation pane, control-click the main database and select **Encrypt Database**.
2. Enter the password in the pop-up window.


Decrypt main database

1. In the Navigation pane, control-click the main database and select **Decrypt Database**.
2. Confirm decrypting in the dialog window.

View the sqlite_master table

1. In the Navigation pane, control-click a database and select **View Master Table**.
2. The sqlite_master table opens in Table Viewer.

Tables

Tables are database objects that contain all data in a database. A table is a set of rows and columns, and their intersections are fields. In the main window, click  **Table** to open the table object list.

You can create a table shortcut by dragging the table out. It provides a convenient way for you to open your table for entering data directly without activating the Navicat main window.

To empty a table, control-click the selected table and select **Empty Table** from the pop-up menu.

Table Designer

Table Designer is the basic Navicat tool for working with tables. It allows you to create, edit and drop table's fields, indexes, foreign keys, and much more.


In the **Fields** tab, you can search a field name by choosing **Edit -> Find -> Find** or pressing COMMAND-F.

Note: The tabs and options in the designer depend on the server version.

Table Viewer

When you open a table, **Table Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.






Views

A view allows users to access a set of tables as if it is a single table. You can use views to restrict access to rows. In the main window, click  **View** to open the view object list.

You can create a view shortcut by dragging the view out. It provides a convenient way for you to open your view without activating the Navicat main window.

View Designer

View Designer is the basic Navicat tool for working with views. You can edit the view definition as SQL statement (SELECT statement it implements) in the **SQL Editor** tab. To customize the view of the editor and find out more features for SQL editing, see [Query Editor](#) for details. If you want to load SQL statement from a SQL file to the editor, you can choose **File -> Import SQL**.

Button	Description
	Preview the data of the view.
	Show the Query Plan of the view.
	Stop the preview process.
	Build the view visually. It allows you to create and edit views without knowledge of SQL. See Query Builder for details.
	Format the codes with the Beautify SQL settings in Editor.

View Viewer

When you open a view, **View Viewer** displays data as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.

Other Objects

Navicat also allows you to manage other SQLite objects: Index and Trigger. In the main window, click  **Others** and select an object to open the object list.

Maintain Objects

Navicat provides a complete solution for maintaining SQLite objects.

1. In the main window, select objects in the Navigation pane or the Objects tab.
2. Control-click the selected objects.
3. Choose **Maintain**, and then choose a maintain option the from the pop-up menu.
4. Results show in a pop-up window.

Database

Option	Description
Analyze Database	Collect statistics about the database.
Vacuum Database	Rebuild the database file. It only works on the main database.
Reindex Database	Delete and recreate all indexes within the database.

Table

Option	Description
Analyze Table	Collect statistics about the contents of the table.
Reindex Table	Delete and recreate all indexes of the table.
Get Rows Count	Count the number of rows in the table.

Index

Option	Description
Reindex	Delete and recreate the index.

MongoDB


Databases



To start working with the server objects, you should create and open a connection. If the server is empty, you need to create a new database.

Create a new database

1. In the Navigation pane, control-click a connection and select **New Database**.
2. Enter the database properties in the pop-up window.

Collections

Collections are analogous to relational database tables for storing documents. In the main window, click  **Collection** to open the collection object list.

You can create **Normal** / **Time Series** collections. To create a new normal collection, simply click  from the object toolbar. Or, you can click and hold the  button and choose the collection type.

You can create a collection shortcut by dragging the collection out. It provides a convenient way for you to open your collection for entering data directly without activating the Navicat main window.

To empty a collection, control-click the selected collection and select **Empty Collection** from the pop-up menu.

Collection Designer


Collection Designer is the basic Navicat tool for working with collections. It allows you to set the collection properties, indexes, validation, storage engine, and much more.

Note: The tabs and options in the designer depend on the server version.

Collection Viewer

When you open a collection, **Collection Viewer** displays data as a grid. Data can be displayed in three modes: Grid View, Tree View and JSON View. See [Data Viewer](#) for details.



Views

A view is the result of the applying the specified aggregation pipeline to the source collection or view. In the main window, click  **View** to open the view object list.

You can create a view shortcut by dragging the view out. It provides a convenient way for you to open your view without activating the Navicat main window.

View Designer

View Designer is the basic Navicat tool for working with views.


Button	Description
	Preview the data of the view.
	Show the Query Plan of the view.

See [Pipeline Builder](#) for details.

View Viewer

When you open a view, **View Viewer** displays data as a grid. Data can be displayed in three modes: Grid View, Tree View and JSON View. See [Data Viewer](#) for details.


Functions

You can store JavaScript functions for reuse. In the main window, click  **Function** to open the function object list.

Function Designer

Function Designer is the basic Navicat tool for working with functions. You can enter the function definition in the **Definition** tab. To customize the view of the editor and find out more features for script editing, see [Query Editor](#) for details.


Results

To execute the function, click  on the toolbar. If the script is correct, a dialog will pop up. Enter input parameters if necessary and click **OK**. If the function is supposed to return data, the **Result** tab opens with the data returned. If an error occurs while executing the function, execution stops, the appropriate error message is displayed.

Indexes

Navicat allows you to manage MongoDB indexes. In the main window, click  **Index** to open the index object list.





MapReduce

Map-Reduce is a data processing paradigm for condensing large volumes of data into useful aggregated results. In the main window, click  **MapReduce** to open the map-reduce object list.


You can set [automation tasks](#) to schedule Map-Reduce jobs.

Map-Reduce Designer


Map-Reduce Designer is the basic Navicat tool for working with Map-Reduce jobs.

Button	Description
	Run the Map-Reduce job.
	Stop the running Map-Reduce job.
	Preview the documents by applying Input, Mapper, Reducer or Finalizer.
	Import an existing function to Mapper, Reducer or Finalizer.

Results

To run the Map-Reduce job, click  on the toolbar. If you set to output the results inline, the **Result** tab opens with the documents returned, the number of documents and the timing information. If you set to write the results to a collection, the results return a document to the specified output collection.

GridFS

GridFS is a specification for storing and retrieving files. In the main window, click  **GridFS** to open the GridFS object list.








You can create multiple buckets in a database for storing files. Click  and enter the name of the bucket.

To open the selected bucket, click .

Bucket Viewer

Bucket Viewer is the basic Navicat tool for working with GridFS buckets. You can upload, download and view GridFS files that are inside the bucket.

Button	Description
--------	-------------


	Open the selected GridFS file.
	Delete the selected GridFS files.
	Upload files into the bucket.
	Download the selected GridFS files.
	Filter the GridFS file table by creating and applying filter criteria.
	Preview an image file that is less than 1 MB.
	Check the status of file uploads and downloads.

File Table

The File table displays all the files that are uploaded to the bucket.



You can edit the GridFS file's name, content type, alias or metadata. In the table, control-click the name of the file and select **Modify File Name**, **Modify Content Type**, **Modify Alias** or **Modify Metadata**. Then, enter the information in the pop-up window.

Filter Pane

If you have many files uploaded to the bucket, you can find matching files using a filter. To toggle the Filter pane, click .

Progress Pane

The Progress pane displays the status of all file uploads and downloads in the current window. Parallel downloads and uploads are supported. If the window is closed, the list will be cleared.

When a file is starting to upload or download, click the corresponding buttons next to the progress bar to pause, resume and stop the process. After the process is finished, you can click  to open the folder that contains the file, or hover over an item and click  to remove it from the list.

If you want to pause, resume and stop all items that are in progress, control-click the list and select the appropriate options.

To clear the finished items, control-click the list and select **Clear All Finished**.

Maintain Objects

Navicat provides a complete solution for maintaining MongoDB objects.

1. In the main window, select objects in the Navigation pane or the Objects tab.
2. Control-click the selected objects.
3. Choose **Maintain**, and then choose a maintain option the from the pop-up menu.
4. Results show in a pop-up window.

Database

Option	Description
Repair Database	Rebuild the database and indexes by discarding invalid or corrupt data.

Collection

Option	Description
Compact Collection	Rewrite and defragment all data and indexes in the collection.
Validate Collection	Check the structures within a namespace for correctness by scanning the collection's data and indexes.
Reindex Collection	Drop and recreate all indexes on the collection.

Redis

Databases

Redis supports 16 databases by default and databases are numbered from 0 to 15. Navicat lists all databases and the number of keys in each database when you connect to your Redis server. Simply double-click a database to open it.

Show / Hide empty databases

1. In the Navigation pane, control-click the connection and select **Show Empty Databases**.

Hint: You can configure Redis to support more databases by adjusting *databases* parameter value in the Redis configuration file (redis.conf). After setting, restart Redis to complete the configuration.

Data

All key-value data in a database is in a data view named **All Data**.

When you open All Data, the viewer displays data as a grid with key names, key types, key values, size and Time-to-Live (TTL). See [Data Viewer](#) for details.

Chapter 6 - Data Viewer

About Data Viewer

Navicat includes a data viewer that allows you to view, update, or delete data. The viewer also includes advanced features and editors that can help you understand the data as you manipulate it. You can use common keyboard navigation to browse your data.













RDBMS

RDBMS Data Viewer

RDBMS Data Viewer displays the data as a grid or a form. To switch the view, click  or  at the bottom.


Note: Form View is available only in Navicat Premium, Enterprise and Standard Edition.

The toolbar of the data viewer provides the following functions for managing data:

Button	Description
	Manage Profile - Manage the saved table profiles and view the profile information. Load Profile - Load a table profile. Save Profile - Create a profile with the current filter, sort and column settings. Save Profile As - Save the settings as a new profile. (Available only in Navicat Premium, Enterprise and Standard Edition)
	Start a transaction. If Auto begin transaction is enabled in Settings , transaction will be started automatically when opening the data viewer.
	Make permanent all changes performed in the current transaction.
	Undo work done in the current transaction.
	Activate the cell editors for viewing and editing data.
	Filter and sort records by applying filter and sorting criteria for the data grid.
	Show / Hide columns .
	Profile the data in the table.
	Generate data for the table.
	Create a new BI workspace with a data source using the table data.
	Import data from files.
	Export data to files.

Use Navigation Bar

Data Viewer provides a convenient way to navigate among the records/pages using the **Navigation Bar** buttons.




Button	Description
+	Add Record - enter a new record. At any point when you are working in the data viewer, click on this button to get a blank display for a record.
-	Delete Records - delete an existing record.
✓	Apply Changes - apply the changes.
✗	Discard Changes - remove all edits made to the current record.
↻	Refresh - refresh the data.
■	Stop - stop when loading enormous data from server.
⏪	First Page - move to the first page.
⏴	Previous Page - move to the previous page.
⏵	Next Page - move to the next page.
⏩	Last Page - move to the last page.
⏶	First Record - move to the first record.
⏴	Previous Record - move one record back (if there is one) from the current record.
⏵	Next Record - move one record ahead.
⏶	Last Record - move to the last record.
⚙️	Setting - set number of records showing on each page.
📊	Grid View - switch to Grid View.
📄	Form View - switch to Form View.

Use the **Setting** ⚙️ button to enter to the edit mode.

Limit records per page

Check this option if you want to limit the number of records showed on each page. Otherwise, all records will be displayed in one single page. And, set the value in the edit box. The number representing the number of records showed per page.

Note: This setting mode will take effect on current object only. To adjust the global settings, see [Settings](#).



Record a of b in page c

Display the numbers representing the selected record and page.

a - the selected record.

b - number of records in the current page.




c - the current page.

Edit Records


Grid View

Grid View is a spreadsheet-like view showing records and fields as rows and columns. The navigation bar allows you to switch the records quickly, insert or delete records.

To add a record

1. Make sure that your cursor is situated in the first blank cell on the table, then enter the desired data. If you are adding the new record into an existing table, just simply click on an existing record and click **+** from the navigation bar or press COMMAND++ to get a blank display for a record.
2. Watch the graphics symbol in the record selectors box just to the left of your record. It will change from , which indicates that it is the current record, to , which indicates that you are editing this record.
3. Just simply move to another record to save the record or click  from the navigation bar.

To edit a record

1. Select the record that you wish to edit by clicking in the specific field you want to change.
2. Type in the new data for that field.
3. Just simply move to another record, the new data will overwrite the previous data or click  from the navigation bar.


Note: Close the table is another way to save the records.

To edit multiple cells with same data

1. Select a block of cells in the data grid.
2. Type in the new data.

Note: Changes will apply to multiple fields with compatible data type.

To delete a record

1. Select the record that you wish to delete.
2. Just simply control-click and select **Delete Record** or click  from the navigation bar.

Form View

Form View displays a single record at a time from a table. The navigation bar allows you to switch the records quickly, insert or delete records.

To add a record

1. Click **+** from the navigation bar or press COMMAND++ to get a blank display for a record.
2. Enter the desired data.

3. Click ✓ from the navigation bar to save the record.

To edit a record

1. Go to the record that you wish to edit.
2. Type in the new data for the specific field you want to change.
3. Click ✓ from the navigation bar. The new data will overwrite the previous data.

Note: Close the table is another way to save the records.

To delete a record




1. Go to the record that you wish to delete.
2. Just simply control-click and select **Delete Record** or click — from the navigation bar.

Edit Records with Special Handling

To set the cell value to an empty string or NULL, click on a cell to enter edit mode, and then control-click the cell and select **Set to Empty String** or **Set to NULL**.

To view images in the grid, just simply choose **View -> Display -> Show Image in Grid**.




Note: Available only for MySQL, Oracle, PostgreSQL, SQL Server and MariaDB.

id	image
1	
2	
3	

Hint: To view/edit images in an ease way, see [Image Editor](#).


To edit a Date/Time record, just simply click ... to open the editor for editing. Choose/enter the desired data. The editor used in cell is determined by the field type assigned to the column.

Note: Available only for MySQL, Oracle, PostgreSQL, SQL Server and MariaDB.

Date	Time	DateTime/Timestamp
		


To edit an Enum record, just simply choose the record from the drop-down menu.

Note: Available only for MySQL, PostgreSQL and MariaDB.



To edit a Set record, just simply click **...** to open the editor for editing. Select the records from the list. To remove the records, uncheck them in the same way. Check **Null** or **Empty Set** to set the value as Null or an empty set.

Note: Available only for MySQL and MariaDB.



To view BFile content, just simply choose **View -> Display -> Preview BFile**.

Note: Available only for Oracle.


To generate UUID/GUID, control-click the selected cell and select **Generate UUID**.

Note: Available only for PostgreSQL and SQL Server.

Edit Records with Foreign Key (Foreign Key Data Selection - Available only in Navicat Premium, Enterprise and Standard Edition)

Foreign Key Data Selection is a useful tool for letting you to get the available value from the reference table in an easy way. It allows you to show additional records from the reference table and search for particular records.


To include data to the record, just simply click **...** to open the editor for editing.



Just simply double-click to select the desired data.


Hint: By default, the number of records showed is **1000**. To show all records, click . To refresh the records, click .

Click to open a pane on the left for showing a list of column names. Just simply click to show the additional column. To remove the columns, uncheck them in the same way.



Hint: To set column in ascending or descending mode, click the right side of the column and select **Sort Asc / Sort Desc**.

Enter a search string into the **Filter** edit box and press ENTER to filter for the particular records.



Hint: To remove the filter results, simply remove the search string and press ENTER.

Copy Data from Grid View

Data that being copied from Navicat goes into the clipboard with the fields delimited by tabs and the records delimited by carriage returns. It allows you to easily paste the clipboard contents into any application you want. Spreadsheet applications in general will notice the tab character between the fields and will neatly separate the clipboard data into rows and columns.

To select data using keyboard shortcuts

COMMAND-A	Toggle the selection of all rows and columns in the data grid.
SHIFT-UP ARROW	Toggle the selection of rows as you move up in the data grid.

SHIFT-DOWN ARROW	Toggle the selection of rows in the data grid as you move down.
------------------	---

To select data using mouse actions

- Select the desired records by holding down the COMMAND key while clicking on each row.
- Select range of records by clicking the first row you want to select and holding down the SHIFT key together with moving your cursor to the last row you wish to select.
- Select a block of cells.

Note: After you have selected the desired records, just simply press COMMAND-C or choose **Edit -> Copy**.

Paste Data into Grid View

Data are copied into the clipboard will be arranged as below format:

- Data are arranged into rows and column.
- Rows and columns are delimited by carriage returns/tab respectively.
- Columns in the clipboard have the same sequence as the columns in the data grid you have selected.

When pasting data into Navicat, you can replace the contents of current records and append the clipboard data into the table. To replace the contents of current records in a table, you must select the cells in the data grid whose contents must be replaced by the data in the clipboard. Just simply press COMMAND-V or choose **Edit -> Paste**. Navicat will paste all the content in the clipboard into the selected cells. The paste action cannot be undone if you do not enable transaction.

Copy Records as Insert/Update Statements

To copy records as Insert/Update statement, control-click the column/row header or the selected cells and select **Copy As -> Insert Statement** or **Update Statement**. Then, you can paste the statements in any editors.

Copy Field Name

To copy field names as tab separated values, control-click the column/row header or the selected cells and select **Copy As -> Tab Separated Values (Field Name only)**. If you want to copy data only or both field names and data, you can choose **Tab Separated Values (Data only)** or **Tab Separated Values (Field Name and Data)** respectively.


Sort / Find / Replace Records

Sort Records

Server stores records in the order they were added to the table. Sorting in Navicat is used to temporarily rearrange records, so that you can view or update them in a different sequence.

Hover over the column caption whose contents you want to sort by, click the right side of the column and select **Sort Asc**, **Sort Desc** or **Remove Sort**.


payment_id	customer_id	rental_id
1		76
2		573
3		1185
4	1	1422



To sort by custom order of multiple columns, click  from the toolbar.



Find and Replace

Find Records


The Find bar is provided for quick searching for the text in the viewer. Just simply choose **Edit-> Find -> Find** or press COMMAND-F. Then, click  and choose **Find Data** and enter a search string. The search starts at the cursor's current position to the end of the file.

To find for the next text, just simply click **>** or press COMMAND-G.

Replace Records

In the Find bar, choose **Replace** or press OPTION-COMMAND-F and enter the text you want to search and replace. Click **Replace** or **Replace All** to replace the first occurrence or all occurrences automatically. If you clicked **Replace All**, you can click  to apply the changes or  to cancel the changes.

Find Columns


To search a column, just simply choose **Edit -> Find -> Find** or press COMMAND-F. Then, click  and choose **Find Column** and enter a search string.

There are some additional options for Find and Replace, click :

Option	Description
Highlight Matched Cells	Highlight all matches in the viewer.
Incremental Search	Find matched text for the search string as each character is typed.
Match Case	Enable case sensitive search.

Filter Records

Use either of the following methods to filter the data in the grid:

- Control-click the cell and select **Filter -> Field xxx Value** from the pop-up menu to filter records by the current value in the cell.
- You can also customize your filter in a more complicated way by clicking  from the toolbar. The Filter & Sort pane becomes visible at the top of the grid, where you can see the active filtering condition and easily enable or disable it by clicking a check box at the left.

Manipulate Raw Data

Navicat normally recognize what user has input in a table as normal string, any special characters or functions would be processed as plain text (that is, its functionality would be skipped).

Editing data in **Raw Mode** provides an ease and direct method to apply server built-in functions. To access Raw Mode, just simply choose **View -> Display -> Raw Mode**.

Note: Available only for MySQL, PostgreSQL, SQLite, SQL Server and MariaDB.

DEPARTMENT_ID	DEPARTMENT_NAME	MANAGER_ID
20	'Marketing'	201
30	'Purchasing'	114
40	CONCAT('Human, ', 'Resources')	203
50	'Shipping'	121
60	'IT'	103

Format Data View

Use the following methods to format the table:

Hint: Form View only supports Show/Hide Columns.

Move Columns

1. Click on the column header and hold down the left mouse button.
2. Move the pointer to the desired location.
3. Release the mouse and the column will move.

Set Column Width

- Click right border at top of column and drag either left or right.
- Double-click right border at top of column to obtain the best fit for the column.
- Control-click the column header and select **Set Column Width** or select from the **View** menu. Specify width in the **Set All Columns Width** dialog.


Hint: The result applies on all columns.

Set Row Height

Control-click the row header and select **Set Row Height** or select from the **View** menu. Specify row height in the **Set Row Height** dialog.

Hint: This action applies on the current table grid only.

Show/Hide Columns

If there are many columns in the table and you want to hide some of them from the grid/form, just simply click . Select the columns that you would like to hide.

The hidden columns will disappear from the grid/form.

To unhide the columns, just simply click . Select the columns that you would like to redisplay.

Show/Hide ROWID

If you want to display or hide the rowid (address) of every row, control-click anywhere on the table grid and select **Show/Hide ROWID** or select from the **View** menu.

The ROWID column will be showed in the last column.

Note: Available only for Oracle and SQLite.

View Field Information

Data Type

You can display the data types of fields in the column header. To do so, control-click the column header and select **Show Field Type**.

EMPLOYEE_ID	FIRST_NAME	LAST_NAME	EMAIL
# double	αβϕ varchar(20)	αβϕ varchar(25)	αβϕ varchar(25)
100	Steven	King	SKING
101	Neena	Kochhar	NKOCHHAR
102	Lex	De Haan	LDEHAAN
103	Alexander	Hunold	AHUNOLD
104	Bruce	Ernst	BERNST

Field Comment




If you have added comments to the table fields, you can control-click the column header and select **Show Comment**. Field comments are displayed as the column header.

Note: Available only for MySQL, Oracle, PostgreSQL, SQL Server and MariaDB.
















actor_id	first_name	last_name	last_update
Actor ID	--	--	--
1	PENELOPE	GUINNESS	2006-02-15 04:3
2	NICK	WAHLBERG	2006-02-15 04:3
3	ED	CHASE	2017-08-31 15:21
4	JENNIFER	DAVIS	2006-02-15 04:3
5	JOHNNY	LOLLOBRIGIDA	2006-02-15 04:3

MongoDB

MongoDB Data Viewer


MongoDB Data Viewer displays the data as a grid or a tree, or in JSON format. To switch the view, click ,  or  at the bottom.


The toolbar of the data viewer provides the following functions for managing data:

Button	Description
	Manage Profile - Manage the saved collection profiles and view the profile information. Load Profile - Load a collection profile. Save Profile - Create a profile with the current filter, sort and column settings. Save Profile As - Save the settings as a new profile. (Available only in Navicat Premium, Enterprise and Standard Edition)
	Start a transaction. If Auto begin transaction is enabled in Settings , transaction will be started automatically when opening the data viewer.
	Make permanent all changes performed in the current transaction.
	Undo work done in the current transaction.
	Activate the cell editors for viewing and editing data. Available only for Grid View and Tree View.
	Filter and sort records by applying filter and sorting criteria for the data grid.
	Show / Hide columns .
	[Tree View] Expand all embedded documents and arrays.
	[Grid View] Collapse all embedded documents. [Tree View] Collapse all embedded documents and arrays.
	[Grid View] Use the specified type color set on the Type Color pane to highlight cells.
	Analyze the collection.
	Generate data for the collection.
	Create a new BI workspace with a data source using the collection data.
	Import data from files.
	Export data to files.

Use Navigation Bar

Data Viewer provides a convenient way to navigate among the documents/pages using the **Navigation Bar** buttons.



Button	Description
	Add Document - enter a new document. At any point when you are working in the data viewer, click on this button to get a blank display for a document.


—	Delete Documents - delete an existing document.
✓	Apply Changes - apply the changes.
✕	Discard Changes - remove all edits made to the current document.
↻	Refresh - refresh the data.
■	Stop - stop when loading enormous data from server.
⏪	First Page - move to the first page.
←	Previous Page - move to the previous page.
→	Next Page - move to the next page.
⏩	Last Page - move to the last page.
📄	First Document - move to the first document.
↑	Previous Document - move one document back (if there is one) from the current document.
↓	Next Document - move one document ahead.
📄	Last Document - move to the last document.
⚙️	Setting - set number of documents showing on each page.
📊	Grid View - switch to Grid View.
📋	Tree View - switch to Tree View.
📄	JSON View - switch to JSON View.

Use the **Setting** ⚙️ button to enter to the edit mode.

Limit documents per page

Check this option if you want to limit the number of documents showed on each page. Otherwise, all documents will be displayed in one single page. And, set the value in the edit box. The number representing the number of documents showed per page.

Note: This setting mode will take effect on current object only. To adjust the global settings, see [Preferences / Settings](#).



Document a of b in page c

Display the numbers representing the selected document and page.

a - the selected document.



b - number of documents in the current page.

c - the current page.

Grid View

Grid View is a spreadsheet-like view showing documents and fields as rows and columns. The navigation bar allows you to switch the documents quickly, insert or delete documents.

To add a document using the grid

1. Click on an existing document and click **+** from the navigation bar or press **COMMAND-+** to get a blank display for a document.
2. Enter the desired data.
3. Watch the graphics symbol in the document selectors box just to the left of your document. It will change from , which indicates that it is the current document, to , which indicates that you are editing this document.
4. Just simply move to another document to save the document or click **✓** from the navigation bar.

Note: If your collection is empty, a window will pop up for you to add documents.

To add a document using the pop-up window

1. Control-click the grid and select **Add Document**.
2. Write the document in the pop-up window.
3. Click **Validate** to ensure the document is correct.
4. Click **Save**.

To edit a document using the grid

1. Select the document that you wish to edit by clicking in the specific cell you want to change.
2. Type in the new data for that cell.
3. Just simply move to another document or click **✓** from the navigation bar, the new data will overwrite the previous data.

To edit a document using the pop-up window

1. Control-click the document that you wish to edit and select **Edit Document**.
2. Edit the document in the pop-up window.
3. Click **Validate** to ensure the document is correct.
4. Click **Save**.


Note: Close the collection is another way to save the documents.

To edit multiple cells with same data

1. Select a block of cells in the data grid.
2. Type in the new data.


Note: Changes will apply to multiple cells with compatible data type.


To delete a document

1. Select the document that you wish to delete.
2. Just simply control-click and select **Delete Document** or click  from the navigation bar.

Edit Documents with Special Handling

To set the cell value to an empty string or NULL, click on a cell to enter edit mode, and then control-click the cell and select **Set to Empty String** or **Set to NULL**.

To edit a DateTime data, just simply click  to open the editor for editing. Choose/enter the desired data.



To change the type of a cell value, click on a cell to enter edit mode, and then control-click the cell and select **Value Type**. Then, select the desired type.

Copy Data from Navicat

Data that being copied from Navicat goes into the clipboard with the fields delimited by tabs and the documents delimited by carriage returns. It allows you to easily paste the clipboard contents into any application you want. Spreadsheet applications in general will notice the tab character between the fields and will neatly separate the clipboard data into rows and columns.

To select data using keyboard shortcuts

COMMAND-A	Toggle the selection of all rows and columns in the data grid.
SHIFT-UP ARROW	Toggle the selection of rows as you move up in the data grid.
SHIFT-DOWN ARROW	Toggle the selection of rows in the data grid as you move down.

To select data using mouse actions

- Select the desired documents by holding down the COMMAND key while clicking on each row.
- Select range of documents by clicking the first row you want to select and holding down the SHIFT key together with moving your cursor to the last row you wish to select.
- Select a block of cells.

Note: After you have selected the desired documents, just simply press COMMAND-C or choose **Edit -> Copy**.

Paste Data into Navicat

Data are copied into the clipboard will be arranged as below format:

- Data are arranged into rows and column.
- Rows and columns are delimited by carriage returns/tab respectively.
- Columns in the clipboard have the same sequence as the columns in the data grid you have selected.

When pasting data into Navicat, you can replace the contents of current documents and append the clipboard data into the collection. To replace the contents of current documents in a collection, you must select the cells in the data grid whose contents must be replaced by the data in the clipboard. Just simply press COMMAND-V or choose **Edit -> Paste**. Navicat will paste all the content in the clipboard into the selected cells. The paste action cannot be undone if you do not enable transaction.

Copy Records as Insert/Update Statements

To copy records as Insert/Update statement, control-click the column/row header or the selected cells and select **Copy As -> Insert Statement** or **Update Statement**. Then, you can paste the statements in any editors.



Copy Field Name


To copy field names as tab separated values, control-click the column/row header or the selected cells and select **Copy As -> Tab Separated Values (Field Name only)**. If you want to copy data only or both field names and data, you can choose **Tab Separated Values (Data only)** or **Tab Separated Values (Field Name and Data)** respectively.

Tree View

Tree View displays documents in a hierarchical view. The navigation bar allows you to switch the documents quickly, insert or delete documents.

To add a document

1. Click  from the navigation bar or press COMMAND++ to get a blank display for a document.
2. Enter the desired data.
3. Click  from the navigation bar to save the document.

Note: If your collection is empty, you need to click  to add a new field.

To edit a document

1. Go to the document that you wish to edit.
2. Click on a field name, a value or a type to modify.

3. Click ✓ from the navigation bar to apply the changes.

To add a field or an item

1. Go to the document that you wish to edit.
2. Click + to add a new field/item.
3. Enter the desired data.

To delete a field or an item

1. Go to the document that you wish to edit.
2. Control-click the field/item you want to delete and select **Delete Value**.

Note: Close the collection is another way to save the documents.


To delete a document

1. Go to the document that you wish to delete.
2. Just simply click - from the navigation bar.

Edit Documents with Special Handling

To set the value to NULL, control-click the selected item and select **Value Type -> NULL**.

To edit a DateTime data, just simply click ... to open the editor for editing. Choose/enter the desired data.



Format Tree View

Expand/Collapse Embedded Documents & Arrays

All embedded Documents and arrays are represented as nodes. The nodes can be expanded or collapsed by clicking the node icon.

<code>_id</code> : 5d8c74417e6b0000040014fb	Object ID ◯
<code>DEPARTMENT_ID</code> : 90	String ◯
▼ <code>DEPARTMENT_NAME</code> : (Document) 2 Fields <code>NAME1</code> : CS <code>NAME2</code> : IT Support +	Document ◯
▼ <code>MANAGER_ID</code> : (Array) 3 Elements 0 : 101 1 : 103 2 : 105 +	Array ◯
<code>LOCATION_ID</code> : 1700	String ◯
+ (under LOCATION_ID)	String ◯
	Double ◯

JSON View

JSON View displays documents in JSON format. The navigation bar allows you to switch the documents quickly, insert or delete documents.

To add a document

1. Click **+** from the navigation bar or press **COMMAND++**.
2. Write the document in the pop-up window.
3. Click **Validate** to ensure the document is correct.
4. Click **Save**.

To edit a document

1. Control-click the document that you wish to edit and select **Edit Document**.
2. Edit the document in the pop-up window.
3. Click **Validate** to ensure the document is correct.
4. Click **Save**.

To delete a document


1. Click on the document that you wish to delete.
2. Just simply click **-** from the navigation bar.

Sort / Find / Replace Documents

Sort Documents

Server stores documents in the order they were added to the collection. Sorting in Navicat is used to temporarily rearrange documents, so that you can view or update them in a different sequence.

Hover over the field caption whose contents you want to sort by, click the right side of the field and select **Sort Asc**, **Sort Desc** or **Remove Sort**.



To sort by custom order of multiple fields, click from the toolbar.

Find and Replace

Find Documents

The Find bar is provided for quick searching for the text in the viewer. Just simply choose **Edit-> Find -> Find** or press COMMAND-F. Then, enter a search string. The search starts at the cursor's current position to the end of the file.

For Grid View or Tree View, you need to click and choose **Find Data**.

To find for the next text, just simply click **>** or press COMMAND-G.

Replace Documents

In the Find bar, choose **Replace** or press OPTION-COMMAND-F and enter the text you want to search and replace. Click **Replace** or **Replace All** to replace the first occurrence or all occurrences automatically. If you clicked **Replace All**, you can click to apply the changes or to cancel the changes.

Find Fields

In Grid View or Tree View, you can search for fields in the collection. Just simply choose **Edit -> Find -> Find** or press COMMAND-F. Click and choose **Find Column**. Then, enter a search string.


There are some additional options for Find and Replace, click :

Option	Description
Highlight Matched Cells	Highlight all matches in the viewer.
Incremental Search	Find matched text for the search string as each character is typed.
Match Case	Enable case sensitive search.

Filter Documents

Use either of the following methods to filter the data in the grid:


- Control-click a cell and select **Filter -> Field xxx Value** from the pop-up menu to filter documents by the current value in the cell.

- You can also customize your filter in a more complicated way by clicking  from the toolbar. The Filter & Sort pane becomes visible at the top of the grid, where you can see the active filtering condition and easily enable or disable it by clicking a check box at the left.

Format Data View



Use the following methods to format the collection grid:

Highlight Cells based on Types

Grid View allows highlighting cells based on data types to make particular cells easy to identify. The Type Color pane is on the right side of the grid. If the grid window is docked to the Navicat main window, you can click the  icon in the Information pane to set the color.


To apply the color, click the  button on the toolbar or check the **Enable Coloring** option on the Type Color pane.

Expand/Collapse Embedded Documents

Grid View allows embedded documents to be expanded alongside other columns for easier data analysis. To expand or collapse an embedded document, just simply click on the cell with embedded document and click  or , or control-click the cell and select **Expand**, **Collapse** or **Collapse All Embedded Documents**.

Public Relations	204	2700
Sales	145	2500
(Document) 2 Fields	(Array) 3 Elements	1700
Finance	108	1700
Accounting	205	1700

Expand Arrays

Grid View allows showing all elements in an array. To expand array elements, just simply click on the cell with array elements and click , or control-click the cell with array elements and select **Expand**.

70	Public Relations	204
80	Sales	145
90	(Document) 2 Fields	(Array) 3 Elements
100	Finance	108
110	Accounting	205

All array elements display on a new grid. You can view, add or delete the elements here. Click the collection name to jump back to the collection grid.

Move Columns

- Click on the column header and hold down the left mouse button.
- Move the pointer to the desired location.
- Release the mouse and the column will move.

Set Column Width

- Click right border at top of column and drag either left or right.
- Double-click right border at top of column to obtain the best fit for the column.
- Control-click on the column header and select **Set Column Width** or select from the **View** menu. Specify width in the **Set All Column Width** dialog.


Hint: The result applies on all columns.

Set Row Height

Control-click on the row header and select **Set Row Height** or select from the **View** menu. Specify row height in the **Set Row Height** dialog.

Hint: This action applies on the current collection grid only.

Show/Hide Columns

If there are many columns in the collection and you want to hide some of them from the collection grid, just simply click . Select the columns that you would like to hide.

The hidden columns will disappear from the collection grid.







To unhide the columns, just simply click . Select the columns that you would like to redisplay.

Redis

Redis Data Viewer


Navicat lets you explore keys in your Redis server using a spreadsheet-like data grid. You can add, edit and delete a key, even update the key expiry using the editor.

The toolbar of the data viewer provides the following functions for managing data:

Button	Description
	Create a profile with the current view of the key data.
	Convert nested data structure to flat format.
	Activate the assistant editor for viewing and editing data.
	Search for keys using a string or a key pattern.
	Display keys in a tabular format, resembling a spreadsheet.
	Display keys in a hierarchical format, showing nested structures.

Use Navigation Bar

Data Viewer provides a convenient way to navigate among the keys using the **Navigation Bar** buttons.




Button	Description
+	Add Key - enter a new key. At any point when you are working in the data viewer, click on this button to get a blank display for a key.
–	Delete Keys - delete an existing key.
Last Refresh	Last Refresh - display the last refresh date and time or the elapsed time since the last refresh.
↻	Refresh - refresh the data.
↓	Fetch More - fetch the next batch size of keys.
⬆	Fetch All - fetch all remaining keys.
⚙	Batch Size Settings - set number of keys showing when opening the data view.

Use the **Batch Size Settings** ⚙ button to enter to the edit mode.

Batch Size

Set the value in the edit box. The number representing the number of keys fetched from the server.

Note: This setting mode will take effect on current data view only.



Edit Keys

Data View is a spreadsheet-like view showing keys as rows and columns. The navigation bar allows you to insert or delete keys.

By default, when opening the data viewer, Navicat loads the number of keys in batch size. If you want to fetch more keys, you can click ↓ or ⬆.

Hint: Newly fetched keys are marked with green indicators. You can unmark them by control-clicking on the grid and selecting **Unmark All Indicators**.

To add a key

1. Click + from the navigation bar or press COMMAND++ to get a blank display for a key.
2. Enter the key properties using the **Editor**.
3. Just simply move to another key to save the key or click **Apply**.


To edit a key

1. Double-click the key that you wish to edit.
2. Type in the new data using the **Editor**.

3. Just simply move to another key or click **Apply**, the new data will overwrite the previous data.

Hint: You can modify key names, key types, key values and time to live (TTL).

To delete a key


1. Select the key that you wish to delete.
2. Just simply control-click and select **Delete Key** or click  from the navigation bar.

Hint: You can hold down the SHIFT or COMMAND key and click to select multiple keys at a time.


Sort Keys


By default, the data grid displays keys in ascending order by key name. Sorting in Navicat is used to temporarily rearrange keys, so that you can view or update them in a different sequence.

Move over the column caption whose contents you want to sort by, click the right side of the column and select **Sort Asc**, **Sort Desc** or **Remove Sort**.




Search Keys


The Search feature is provided for quick searching for keys in the database. Just simply choose the data type and enter a key name in the **Search** box. Then, click  or press ENTER.

There are some additional options for Search, click :

Option	Description
Keys Contain	Return all keys contains the search string (case insensitive).
Keys Contain (Match Case)	Enable case sensitive search.
Keys Match Pattern	Return all keys matching the pattern.

To remove the search, just simply click .

Cell Editors




Navicat provides powerful cell editors to view and edit fields content. The editor allows you to view, update, insert, or delete data in a table or a collection. Click  from the toolbar to activate the appropriate viewer/editor.

Note: Oracle BFile fields cannot be edited. MongoDB JSON View does not support cell editors.

[MySQL](#), [Oracle](#), [PostgreSQL](#), [SQLite](#), [SQL Server](#), [MariaDB](#), [MongoDB](#)


The **Text** pane allows you to edit data as a simple text. To change the syntax highlight, simply control-click the empty space and select **Language**. Use the ✓ button on the navigation bar to update the changed records or documents.

The **Hex** pane allows you to edit data in hexadecimal mode. Use the ✓ button on the navigation bar to update the changed records or documents.

The **Image** pane allows you to show data as image. Use the  **Load**,  **Save to disk** and  **Clear** buttons to load/remove the image from a file, and save the image to a file.



The **Web** pane allows you to show data with HTML codes as in a web browser.

Filter & Sort Pane

The Filter & Sort pane allows you to facilitate applying filter and sorting criteria that you specify for the data grid. Click  from the toolbar to activate the Filter & Sort pane.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB.

Apply Filter

1. To add a new condition to the criteria, just simply click . If you want to add a condition with parentheses, click .

Hint: To add parentheses to existing conditions, simply control-click on the selected conditions and select **Group with Bracket**. To remove the parentheses, control-click a bracket and select **Delete Bracket** or **Delete Bracket and Conditions**.

2. Click on the field name (next to the checkbox) and choose a field from the list.
3. Click on the operator (next to the field name) and choose a filter operator. You can choose **[Custom]** from the list to enter the condition manually.




Filter Operator	Operator Description
=	The field is equal to 'value'.
!=	The field is not equal to 'value'.
<	The field is less than 'value'.
<=	The field is less than or equal to 'value'.
>	The field is greater than 'value'.
>=	The field is greater than or equal to 'value'.
contains	The field contains 'value'.
contains (case insensitive)	The field contains 'value' (case insensitive). Available only for PostgreSQL.
does not contain	The field does not contain 'value'.
does not contain (case insensitive)	The field does not contain 'value' (case insensitive). Available only for PostgreSQL.
begin with	The field starts with 'value'.

does not begin with	The field does not start with 'value'.
end with	The field ends with 'value'.
does not end with	The field does not end with 'value'.
is null	The field is NULL.
is not null	The field is NOT NULL.
is empty	The field is empty.
is not empty	The field is not empty.
is between	The field is between 'value1' and 'value2'.
is not between	The field is not between 'value1' and 'value2'.
is in list	The field is in the list of ('value1','value2',...).
is not in list	The field is not in the list of ('value1','value2',...).
exists	The field exists. Available only for MongoDB.
does not exist	The field does not exist. Available only for MongoDB.
is field type	The field type is 'value'. Available only for MongoDB.
is not field type	The field type is not 'value'. Available only for MongoDB.

- Click on ? to activate the appropriate editor and enter the criteria values. The editor used in the criteria values box is determined by the data type assigned to the corresponding field.
Hint: For MongoDB, you can change the editor type in the criteria values box.
- Click on the logical operator (next to the criteria values) to choose **and** or **or**.
- Repeat step 1-5 to add another new condition.
- Click **Apply Filter & Sort** to see the result of the filtering you made.

Hint: If you want to reverse the meaning of the conditions, control-click the selected conditions and select **Toggle Negator**. (Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server and MariaDB)

Apply Sort

- Click .
- Click on the field name and choose a field you want to sort from the list.
- Click  or  to change the sorting order.
- Repeat step 1-3 to add another field.
- Click **Apply Filter & Sort** to see the result of the sorting you made.

Hint: If you have more than one field in the **Sort by** area, you can rearrange the order by dragging the fields into the precise position you want.

Change Layout

You can change the appearance of the Filter & Sort pane: **Tabbed** or **Integrated**. In the tabbed layout, the filter and sort options are compartmentalized into individual tabs for organization. Conversely, the integrated layout consolidates the filter and sort options into a unified pane.

To access these layout options, you can choose **View -> Filter & Sort Layout**.

Chapter 7 - Data Profiling (Available only in Navicat Premium, Enterprise and Standard Edition)

About Data Profiling

The Data Profiling tool in Navicat allows you to gain comprehensive insights into your data. This information helps you to better understand your data assets, identify data quality issues, make informed decisions about data usage, and ensure the data meets the required standards for analysis.

It offers various functionalities to assist you in exploring your data. It enables you to examine data types, formats, distributions, and statistical properties within your datasets. You can easily identify missing values, outliers, and data inconsistencies, ensuring data accuracy and completeness.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server and MariaDB.


Start Data Profiling


Data profiling is resource intensive and execution times can be quite long, especially with large data volumes. Besides profiling all records, you can use filter to select the data that a profile scans. If you add a filter, the profile scans only on the data values that meet the filter criteria that you specify.

To enable the Data Profiling tool, open a table and click . In the Data Profiling pane, enable the profiling options you want and click **Start Profiling**.

Option	Description
All Records	All data in the table is scanned in the data profiling scan.
Add Filter	You can filter data to be scanned for profiling and set a range of records (No Limit or First # records) to sample for running profiling scan.

View Profiling Results

After the profiling finished, the data profile results appear. The results show all the columns and their statistics in the profile run. You can modify the profiling options by clicking  and then re-profile the data.




Column Quality & Distribution


The Column Quality & Distribution pane provides the quality of the data in terms of distinct values, unique values, NULL values and non-NULL values, also it displays column distribution charts associated with the column values.

Column Quality

The column quality includes a small bar chart and column quality categories (displayed as percentages). It displays directly underneath the column name.




By hovering over any category, it will show you the numerical distribution of the value qualities throughout the column.



Column Distribution

In column distribution charts, you can see the frequency and distribution of the values in each of the columns as in histogram.

By default, the data in these visualizations is sorted in ascending order of the values. You can change the sorting order and category by control-clicking the chart and select **Sort Distribution**.




By hovering over any bar, it will show you the value and the numerical distribution of the quality of that value throughout the column.

You can change the display style that works best for you by control-clicking a bar and choosing **Compact** or **Detailed**. Compact View hides Column Quality information, while Detailed View shows both Column Quality & Distribution information.

Column Statistics

The Column Statistics pane provides a more in-depth look at the data in a column. It contains column statistics with distribution measures like Count, Distinct, Unique, Empty String, Min, Max. Apart from the value distribution, you can select a measure to shown a column statistics chart.



Add Spotlight

Use spotlights to draw attention to specific values on the profiling result. To spotlight values, use one of the following methods:

- Click a column quality category or a bar in the Column Quality & Distribution pane.
- Control-click a bar in the Column Quality & Distribution pane and select **Spotlight This Value** or **Add Spotlight**.
- Control-click a value in the grid and select **Spotlight This Value** or **Add Spotlight**.
- Control-click a bar in the Value Distribution chart and select **Spotlight This Value** or **Add Spotlight**.

Hint: Remove the spotlighted values in the same way.

payment_id	customer_id	staff_id	rental_id	amount	payment_date	last_update
11031	407	2	15334	1.99	2005-08-22 20:44:35	2006-02-15 22:18:00
11032	408	2	3	3.99	2005-05-24 23:03:39	2006-02-15 22:18:00
11033	408	2	59	5.99	2005-05-25 08:56:42	2006-02-15 22:18:00
11034	408	1	526	2.99	2005-05-28 04:27:37	2006-02-15 22:18:01
11035	408	2	2479	4.99	2005-06-18 21:03:08	2006-02-15 22:18:01
11036	408	1	2564	2.99	2005-06-19 03:41:10	2006-02-15 22:18:01


Column Statistics

amount


Spotlight Field: amount
Spotlight Values: 2.99, 3.99

Count	4651
Null	0 0%
Not Null	4651 100%
Zero	0 0%
NaN	0 0%
Distinct	2

Value Distribution





Copy Column Statistics

In the Column Statistics pane, you can hover over a measure and click .

Chapter 8 - Query

About Query











A query is used to extract data from the database in a readable format according to the user's request. Navicat provides powerful tools for working with queries: Query Editor for editing the query text directly, and Query Builder, Find Builder or Aggregate Builder for building queries visually. You can save your queries for setting [automation tasks](#). In the main window, click  **Query** to open the query object list. You can also click  **New Query** in the main toolbar to create a new query without opening any connections.

To open a query using an external editor, control-click it and select **Open with External Editor**. You can set the file path of an external editor in [Settings](#).

Hint: Queries (.sql, .js or .redis) are stored under the [Settings Location](#). To open the folder, control-click a query and select **Show in Finder**. If the connection is synchronized to [Navicat Cloud](#) or [On-Prem Server](#), its queries will be stored in the cloud.

Query Designer

Query Designer is the basic Navicat tool for working with queries.

Button	Description
MySQL, Oracle, PostgreSQL, SQLite, SQL Server and MariaDB	
	Open the Query Builder for building queries visually.
	Format the codes with the Beautify SQL settings in Editor.
	Show the execution plan of the query: Explain or Explain Selected (when highlighted code).
MongoDB	
	Open the Find Builder for building queries visually.
	Open the Aggregate Builder for building queries visually.
	Format the codes in Editor.
	Show the execution plan of the query: Explain or Explain Selected (when highlighted code).
Common	
	Show the Code Snippet pane.
 Run	Run - Execute the entire query. Run Current Statement - Execute the current statement based on the cursor position. Run Selected - Execute the highlighted code. Continue on Error - Ignore errors that are encountered during the execution process. (MongoDB does not support Run Current Statement and Continue on Error.)
	Stop the executing query.

Create BI workspace using the query as a data source

1. In Query Designer, choose **File -> Create BI Workspace**.

Open an external file in Navicat

1. In the menu bar, choose **File -> Open External File -> Query**.
2. Select the file.
3. Click **Open**.

Save an opened external file as a Navicat query

1. In Query Designer, choose **File -> Save to Navicat**.
2. Enter the query name and choose the save location.
3. Click **OK**.

Save a Navicat query as an external file

1. In Query Designer, choose **File -> Save As External File**.
2. Choose the save path and enter the file name.
3. Click **Save**.

RDBMS

Query Editor

Query Editor allows you to create and edit SQL text, prepare and execute selected queries. You can define multiple SQL statements in one query window. Drag-and-drop or double-click an identifier in the right **Identifiers** pane to add it to the editor.

Hint: SELECT statement will be automatically generated in Query Editor while you build in Query Builder.

Navicat provides a wide range advanced features, such as compelling code editing capabilities, smart code-completion, SQL formatting, and more.

SQL Formatting

To change the SQL statement format, simply choose from the **Format** menu -

Indent

Increase/decrease indent for the selected lines of codes.

Comment

Comment/uncomment the selected lines of codes.

Convert Case

Format the selected codes into upper/lower case.

Beautify SQL

Format the selected codes with the Beautify SQL settings.

Beautify SQL With

Change the SQL beautifier options.

Option / Button	Description
Short Brace Length	Set the length of the short brace.
Upper case keywords	Format all the SQL keywords to upper case.
Beautify	Save and apply the SQL beautifier options.

Minify SQL


Minify the format of the SQL in the Query Editor.

Code Completion

Code completion feature in Navicat pops up a list of suggestions as you type your SQL statement in the editor. It assists you with statement completion and the available properties of database objects, for example databases, tables, fields, views etc with their appropriate icons and information. You can update the code suggestions with latest database information by choosing **Edit -> Code Completion -> Update Code Completion Info**.


To invoke code completion, just simply press '.' for the available properties of database object currently in the scope.

When the suggestion list appears, press TAB to insert the first item. You can also select the needed item using UPPER ARROW or DOWN ARROW and then press TAB or ENTER.



In addition, code completion can be invoked by typing a character or pressing ESC on your keyboard for SQL keywords/database objects.

If you select a snippet name from the list, the saved code will be inserted to the editor.



Hint: Resize the suggestion list by dragging the lower right corner.





You can enable or disable the code completion feature in [Settings](#).

Clipboard Stack






When you copy or cut some codes as usual in the editor, the copied content will also be added to Clipboard Stack. Clipboard Stack can store up to 10 items and use the last-in-first-out logic. To paste an item from Clipboard Stack, you can press COMMAND-SHIFT-V. Press COMMAND-SHIFT-V multiple times to cycle through Clipboard Stack.

Code Folding

Code folding feature enables you to collapse blocks of code such that only the first line of the block appears in Query Editor.

A block of code that can be folded is indicated by an icon  to the left of the first line of the block. A vertical line extends from the icon to the bottom of the foldable code. In contrast, a folded block of code is indicated by an icon  to left of the code block. You can fold the block by clicking  or expand it by clicking .

```

1  SELECT
2   IFNULL(
3       SUM(
4           IF
5           ((  ...
10         0
11     ) INTO v_overfees
12 FROM
13     rental,
14     inventory,
15     film
16 WHERE
17     film.film_id = inventory.film_id
18     AND inventory.inventory_id = rental.inventory_id
19     AND rental.rental_date <= p_effective_date
20     AND rental.customer_id = p_customer_id;

```

Syntax Highlight

Navicat uses syntax highlighting which depending on the database associated with the query. Different databases have different sets of reserved keywords. You can configure the associated colors for different text fragments in [Settings](#).

Brace Highlight

Navicat supports to highlight the matching brace in the editor, i.e. () .

Note: The cursor must be on a brace to show the highlight.

```
1 SELECT
2 IFNULL(
3 SUM(
4 IF
5 (
6 TO_DAYS( rental.return_date ) - TO_DAYS( rental.rental_date )) > film.rental_duration,
7 (( TO_DAYS( rental.return_date ) - TO_DAYS( rental.rental_date )) - film.rental_duration ),
8 0
9 ),
10 0
11 ) INTO v_overfees
12 FROM
```

Find and Replace

Find

The Find bar is provided for quick searching for the text in the editor. Just simply choose **Edit -> Find -> Find** from the menu or press **COMMAND-F**, and then enter a search string.

Incremental searching is used here. As you type, the matched text is found and highlighted instantly. This saves your time from typing the entire text.

The search starts at the cursor's current position to the end of the file.

To find the previous or next occurrence, just simply click **◀** or **▶**.

Replace

To open the Replace bar, simply choose **Edit -> Find -> Find and Replace** from the menu bar or press **OPTION-COMMAND-F**. Then, enter the text you want to search and replace.

Click the **Replace** button to replace the first occurrence.

Click the **Replace All** button to replace all occurrences automatically.

There are some additional options for Find and Replace, click **🔍**:

Option	Description
Regular Expression	Search regular expressions.
Match Case	Enable case sensitive search.
Whole Words	Return the objects that match the entire word of the search string.

Copy with Quotes

To copy the SQL statement with quotes, just simply control-click the highlighted SQL. Then, select **Copy with Quotes** and choose the format.

Word Wrap

In the Word Wrap mode, the horizontal scrollbar is removed. SQL statement that exceeds the width of the editor window size wraps to the next line. To enable Word Wrap, choose **View -> Word Wrap**.

Zoom In/Zoom Out

Navicat has the ability to zoom in or zoom out the SQL in the editor. The zooming options are available from the **View** menu. The same effect can be achieved with keyboard shortcuts.

Zoom In: [COMMAND+]

Zoom Out: [COMMAND--]

Reset: [COMMAND-0]

Note: Editors that are opened in different tabs or windows will not be affected by the zoom.


Query Builder (Available only in Navicat Premium, Enterprise and Standard Edition)

Navicat provides a useful tool called **Query Builder** for building queries, views and materialized views visually. It allows you to create and edit queries without knowledge of SQL. Even if you are familiar with SQL, the convenient and fluent graphical interface makes it easier to create relations and visualize the query.

In Query Designer, click the  button to open the visual Query Builder.

All database objects are displayed on the left **Object** pane. Whereas on the middle pane, it is divided into two portions: the upper **Diagram** pane, and the lower **Criteria** pane. When building the query, you can view the auto-generated query on the right **SQL** pane.

Note: Query Builder supports SELECT statement only. Use Query Editor for creating other complex queries (e.g. INSERT, UPDATE, DELETE).



Add Objects to Query

The first step is to decide which tables and views you need to add to the query.

To add tables and views to the query, use one of the following methods:

- Drag them from the Object pane to the Diagram pane.
- Double-click them on the Object pane.

You can set aliases for tables, views and subqueries by double-clicking the object title on the Diagram pane and entering the name to use as an alias for the object name.

After you have added objects to the diagram, you can use the **FROM** tab to adjust the query to your needs.

- To change the object, click the object and select an identifier.
- To add the table alias, click **<Alias>**.



You can control-click an object on the Diagram pane and select **Remove**, or simply press DELETE key to remove the selected object from the query.

When you remove an object, Query Builder automatically removes joins that involve that object.

Choose Output Fields

To include fields in the query, use one of the following methods:

- Check the left checkbox of a field name you want to add to the query on the Diagram pane.
- To include all the fields for an object, check the * checkbox on the Diagram pane.
- To add all fields for all objects, click **+** on the **SELECT** tab and select **All fields(*)**.

The selected fields display on the **SELECT** tab. You can specify additional output field options.


- Check the **DISTINCT** checkbox to force the query to return distinct results.
- To add the field alias, click **<Alias>** and enter the name.
- Click the identifier and select the **Aggregate** function.
- Use the up arrow and down arrow buttons to change the order of fields.

Set Field Association

Query Builder will automatically join the tables as per the foreign key relations. If you want to associate database objects manually, just select a field from an object and drag it to a field in another object. A connector line appears between the two objects to visually represent the relationship and the join type.


There are two views to show the connector lines: Table Relation and Field Relation. The **Field Relation** view allows you to identify matching fields in two tables, while the **Table Relation** view displays the join relationship between the two tables.

All joins are initially created as INNER JOIN by default. To change the association, click or double-click the connector line on the Diagram pane or click the JOIN keyword on the **FROM** tab, and then select a join type. If a join type is not listed, you can enter a customized one in the **Custom** textbox.



To remove a join, control-click the connector line and select **Remove**.

To modify the join condition, control-click a connector line and select **Edit Join**, or click the condition on the **FROM** tab.




The pop-up menu options of the FROM tab:


Option	Description
--------	-------------

Insert	Add an identifier, an expression or a subquery.
Insert Bracket	Add a pair of parentheses.
Remove	Remove the identifier, expression or subquery.
Edit SQL	Edit the subquery.
Convert to Subquery	Convert the condition to a subquery.
Clear and Convert to USING Clause	Remove the ON condition and convert it to USING clause.
Clear and Convert to ON Clause	Remove the USING condition and convert it to ON clause.
Group with Bracket	Add parentheses to group the selected conditions.
Ungroup	Remove the parentheses.

Set Filter Criteria

When retrieving data, you may want to set up a filtering expression. To filter data returned by the query, control-click a field on the Diagram pane and select **Add Field To -> WHERE** and an operator.

The condition is added to the **WHERE** tab. You can edit the value there by clicking **<Value>**. If you want to add a condition with parentheses, click . You can change a logical operator (and/or) by clicking it. Use the up arrow and down arrow buttons to change the order of conditions.



The pop-up menu options of the WHERE tab:

Option	Description
Toggle Negator	Reverse the meaning of the condition.
Insert	Add a condition.
Insert Custom	Add a custom condition.
Insert Bracket	Add a pair of parentheses.
Remove	Remove the condition.
Group with Bracket	Add parentheses to group the selected conditions.
Ungroup	Remove the parentheses.

Group Resulting Data

You can set the conditions for grouping query records by control-clicking a field in the Diagram pane and selecting **Add Field To -> GROUP BY -> Add Field**.

The condition is added to the **GROUP BY** tab. Use the up arrow and down arrow buttons to change the order of fields.

On the **HAVING** tab, you can filter summarized data or grouped data. Select the identifiers, operators, aggregate or enter expressions to include in the condition. Use the up arrow and down arrow buttons to change the order of conditions.

The pop-up menu options of the HAVING tab:

Option	Description
Toggle Negator	Reverse the meaning of the condition.
Insert	Add a condition.
Insert Custom	Add a custom condition.
Insert Bracket	Add a pair of parentheses.
Remove	Remove the condition.
Group with Bracket	Add parentheses to group the selected conditions.
Ungroup	Remove the parentheses.

Sort Resulting Data

You can set the way of sorting query records by control-clicking a field on the Diagram pane and selecting **Add Field To -> ORDER BY -> ASC** or **DESC**. The condition will be added to the ORDER BY tab.

Limit Resulting Data

On the **LIMIT** tab, you can limit your query results to those that fall within a specified range.

Offset


Specify the number of records to be skipped. It is optional.

Limit


Specify the number of records to be displayed.


Note: Available only for MySQL, PostgreSQL, SQLite and MariaDB.

Add Expressions/Subqueries

You can add an expression or a subquery to further limit the query results. On the **FROM** tab, click  and select the **Expression/Subquery** tab.

After entered an expression or a subquery, confirm editing by pressing the ENTER key. It will be added to the Diagram pane indicates that the statement contains an expression or a subquery and identifies the columns it is on.



By clicking the  button, you will be switched to a subquery layer where you can build it visually in the same way as the main query.

You can always go back to the main query by clicking **(Main Query)**.

View Generated SQL


The **SQL** pane presents a read-only, formatted representation of the SQL generated by Query Builder. You can copy the SQL that appears in the SQL pane for use in other tools. In a subquery layer, you can enable **Show Current Layer Only** to show the subquery SQL.

Query Parameters

Query supports using of parameters inside the query text. You can set query parameters to add variable values to a query each time you run it. The parameter should appear as an identifier with \$ at its beginning, quote with [], e.g. [\$any_name].


Execute the query and the **Input Parameters** dialog is provided for you to enter the desired data you wish to search. Check the **Raw Mode** option to pass the inputted values to the query without quotation marks.

Debug Oracle Query (Available only in Navicat Premium, Enterprise and Standard Edition)

To debug an Oracle query, click  on the toolbar to launch the [Oracle Debugger](#).





Enter the parameters if the query has input parameters.

Query Results



You can run the query in any servers. Select the target connection, database and/or schema from the drop-down menu on the toolbar, and then click . If the query statement is correct, the query executes and, if the query statement is supposed to return data, the **Result** tab opens with the data returned by the query. If an error occurs while executing the query, execution stops, the appropriate error message is displayed.

The **Result** tab displays the result data, returned by the query, as a grid. Data can be displayed in two modes: Grid View and Form View. See [Data Viewer](#) for details.



Button	Description
--------	-------------

	Activate the cell editors for viewing and editing data.
	Profile the data in the query.
	Export the result of the query.
	Pin the tab.


Note: Navicat supports to return 20 result sets.


You are allowed to run selected portion of query, just simply highlight SQL in Query Editor and click . To run the current statement your cursor is on (position the cursor within the desired statement), just simply click and hold the  button and select **Run Current Statement**.

Adjust Result Position

In Navicat, you have the flexibility to configure how query results are displayed. You can choose to show the query results on an entire page, on the right side of the editor, or at the bottom of the editor. This allows you to adapt the display layout based on your specific needs and preferences during data analysis and exploration in Navicat. To change the result position, use the  or  icon located in the upper right corner, or access the **View -> Result** menu.

Pin Query Result (Available only in Navicat Premium, Enterprise and Standard Edition)

Existing result tabs are removed when you re-execute the query. You can pin a result tab so that it remains visible after re-executing the query. Simply click  and its contents will not be cleared the next time you execute it.

When you pin a tab, it will display a pin icon and automatically moves towards the left side of the tab bar. All pinned tabs appear from left to right in the order you pinned. Hover over a pinned tab will show its execution time and the query. You can pin any number of results and quickly see what's pinned and what's not pinned. Simply click  to unpin a tab.

Custom Tab Name





To customize the names of the result tabs, simply add `-- NAME:tab_name` or `/*NAME:tab_name*/` before each SELECT statement in the Query Editor.

```

1  -- NAME:actor
2  SELECT * FROM actor;
3  |
4  -- NAME:customer
5  SELECT * FROM customer;
6


```

Message Summary actor **customer**

Data Info    

customer_id	store_id	first_name	last_name	email	address_id
	1	2 MARY	SMITH	MARY.SMITH@sa	5
	2	1 PATRICIA	JOHNSON	PATRICIA.JOHN	6
	3	1 LINDA	WILLIAMS	LINDA.WILLIAMS	7
	4	2 BARBARA	JONES	BARBARA.JONES	8
	5	1 ELIZABETH	BROWN	ELIZABETH.BRO	9
	6	2 JENNIFER	DAVIS	JENNIFER.DAVIS	10
	7	1 MARIA	MILLER	MARIA.MILLER@	11
	8	2 SUSAN	WILSON	SUSAN.WILSON@	12
	9	2 MARGARET	MOORE	MARGARET.MOO	13

Show Query Profiling and Status (Available only for MySQL and MariaDB)

To show the query profiling and status when running the query, simply choose **View -> Show Query Profiling and Status** and click  on the toolbar.


The **Query Profiling** tab under the Result tab displays the query profiling: Table lock, System lock, Statistic, etc.

Note: For MySQL 5.0, supported from 5.0.37. For MySQL 5.1, supported from 5.1.24.


The **Status** tab displays the query status: Bytes received, Bytes sent, etc.

Query Explain

Query Explain provides detailed information about how a database query is executed by the database server. It helps you understand and optimize the performance of queries by analyzing the query execution plan.

When you click , Navicat sends an EXPLAIN statement to the database server. The server then generates an execution plan that outlines the steps it will take to execute the query and retrieve the requested data.




The **Explain** tab displays the execution plan. You can pin the tab by clicking .

You are allowed to explain selected portion of query, just simply highlight SQL in Query Editor and click .

Note: The supported plan formats depend on the server types.

Execution Plan - Visual (Available only in Navicat Premium, Enterprise and Standard Edition)

The diagram displays the operations performed by the query and the data passed between them. If the cost of an operation equals or exceeds the threshold value in the diagram, the number turns red. Click on an operation to view its statistical information. The information helps to understand what is happening internally when the query is executed.

Button / Option	Description
Cost Threshold(%)	Set the threshold value to determine when certain operations in the execution plan are considered important enough to be marked red.
	Zoom in or zoom out the diagram.
	Download the diagram as a PNG file.
	Filter the nodes in the diagram by the node type.
Find	Enter a search string to find matches.

Execution Plan - JSON

The text-based plan provides a complete set of information about the query execution displayed in JSON format. This format can be difficult to read and analyze, but is easy to share with others.

Execution Plan - Text

The text-based plan provides a complete set of information about the query execution.

Execution Plan - Grid

The grid-based plan provides a complete set of information about the query execution.

Execution Plan - Statistic

Per Node Type - It shows the summary information of each node type in the visual graph.

Per Relation - It shows the statistical information that related to each table.

MongoDB

Query Editor

Query Editor allows you to create and edit a script, prepare and execute selected script. Drag-and-drop or double-click an identifier in the right **Identifiers** pane to add it to the editor.

Hint: Script will be automatically generated in Query Editor while you build in Find Builder or Aggregate Builder.

Navicat provides a wide range advanced features, such as compelling code editing capabilities, smart code-completion, script formatting, and more.

Script Formatting

To change the script format, simply choose from the **Format** menu -

Indent

Increase/decrease indent for the selected lines of codes.

Comment

Comment/uncomment the selected lines of codes.


Beautify Script

Format the selected codes.

Code Completion


Code completion feature in Navicat pops up a list of suggestions as you type your script in the editor. It assists you with database names, collection names, view names, document field names and shell methods with their appropriate icons and information. You can update the code suggestions with latest database information by choosing **Edit -> Code Completion -> Update Code Completion Info**.

Code completion can be invoked by typing a dot (.), a character or pressing ESC.



When the suggestion list appears, press TAB to insert the first item. You can also select the needed item using UPPER ARROW or DOWN ARROW and then press TAB or ENTER.

If you select a snippet name from the list, the saved code will be inserted to the editor.



Hint: Resize the suggestion list by dragging the lower right corner.





You can enable or disable the code completion feature in [Settings](#).

Clipboard Stack

When you copy or cut some codes as usual in the editor, the copied content will also be added to Clipboard Stack. Clipboard Stack can store up to 10 items and use the last-in-first-out logic. To paste an item from Clipboard Stack, you can press COMMAND-SHIFT-V. Press COMMAND-SHIFT-V multiple times to cycle through Clipboard Stack.

Code Folding

Code folding feature enables you to collapse blocks of code such that only the first line of the block appears in Script Editor.

A block of code that can be folded is indicated by an icon  to the left of the first line of the block. A vertical line extends from the icon to the bottom of the foldable code. In contrast, a folded block of code is indicated by an icon  to left of the code block. You can fold the block by clicking  or expand it by clicking .



Syntax Highlight

Navicat uses syntax highlighting which depending on the database associated with the query. Different databases have different sets of reserved keywords. You can configure the associated colors for different text fragments in [Settings](#).

Brace Highlight

Navicat supports to highlight the matching brace in the editor, i.e. () .

Note: The cursor must be on a brace to show the highlight.

```
1 db.getCollection("employees").find({
2   $or: [{
3     $and: [{
4       "DEPARTMENT_ID": 105
5     }, {
6       "JOB_ID": "T190"
7     }]
8   }, {
9     "MANAGER_ID":
10  }]
11 })
```

Find and Replace

Find

The Find bar is provided for quick searching for the text in the editor. Just simply choose **Edit -> Find -> Find** from the menu or press COMMAND-F, and then enter a search string.

Incremental searching is used here. As you type, the matched text is found and highlighted instantly. This saves your time from typing the entire text.

The search starts at the cursor's current position to the end of the file.

To find the previous or next occurrence, just simply click ◀ or ▶ .

Replace

To open the Replace bar, simply choose **Edit -> Find -> Find and Replace** from the menu bar or press OPTION-COMMAND-F. Then, enter the text you want to search and replace.

Click the **Replace** button to replace the first occurrence.

Click the **Replace All** button to replace all occurrences automatically.

There are some additional options for Find and Replace, click 🔍 :

Option	Description
Regular Expression	Search regular expressions.
Match Case	Enable case sensitive search.
Whole Words	Return the objects that match the entire word of the search string.

Copy with Quotes

To copy the script with quotes, just simply control-click the highlighted script. Then, select **Copy with Quotes** and choose the format.

Word Wrap

In the Word Wrap mode, the horizontal scrollbar is removed. Script that exceeds the width of the editor window size wraps to the next line. To enable Word Wrap, choose **View -> Word Wrap**.

Zoom In/Zoom Out

Navicat has the ability to zoom in or zoom out the script in the editor. The zooming options are available from the **View** menu. The same effect can be achieved with keyboard shortcuts.

Zoom In: [COMMAND-+]

Zoom Out: [COMMAND--]

Reset: [COMMAND-0]

Note: Editors that are opened in different tabs or windows will not be affected by the zoom.

Find Builder (Available only in Navicat Premium, Enterprise and Standard Edition)

Navicat provides Find Builder for building queries visually to select documents in a collection or view. It allows you to create and edit queries without knowledge of the *find* command.

In Query Designer, click the  button to open the visual Find Builder.

Select the name of the collection or view to query from the **Collection/View** drop-down menu.

Filter

In this tab, you can specify selection filters for the query. Documents that meet the conditions will be returned. If you not specify the filter, all documents will be returned. See [Filter & Sort](#) for details.

Projection

In this tab, you can choose which fields to include or exclude in the returned documents. If you not specify the projection, all fields will be returned.

Sort

In this tab, you can sort the returned documents by fields in ascending or descending order.

Limit


In this tab, you can limit the maximum number of documents to return and set the number of documents to skip.

Aggregate Builder (Available only in Navicat Premium, Enterprise and Standard Edition)





Navicat provides Aggregate Builder for building queries visually to return computed results. It allows you to create and edit queries without knowledge of the *aggregate* command.

In Query Designer, click the  button to open the visual [Aggregate Builder](#).


Query Results

You can run the query in any servers. Select the target connection and database from the drop-down menu on the toolbar, and then click . If the query script is correct, the query executes and, if the query script is supposed to return data, the **Result** tab opens with the data returned by the query. If an error occurs while executing the query, execution stops, the appropriate error message is displayed.



The **Result** tab displays the result data, returned by the query, as a grid. Data can be displayed in three modes: Grid View, Tree View and JSON View. See [Data Viewer](#) for details.

Button	Description
	Activate the cell editors for viewing and editing data.
	[Grid View] Use the specified type color set on the Type Color pane to highlight cells.
	Export the result of the query.
	Pin the tab.


Note: Navicat only returns the last result data.


You are allowed to run selected portion of query, just simply highlight script in the editor and click .

Adjust Result Position

In Navicat, you have the flexibility to configure how query results are displayed. You can choose to show the query results on an entire page, on the right side of the editor, or at the bottom of the editor. This allows you to adapt the display layout based on your specific needs and preferences during data analysis and exploration in Navicat. To change the result position, use the  or  icon located in the upper right corner, or access the **View -> Result** menu.


Pin Query Result (Available only in Navicat Premium, Enterprise and Standard Edition)


Existing result tabs are removed when you re-execute the query. You can pin a result tab so that it remains visible after re-executing the query. Simply click  and its contents will not be cleared the next time you execute it.


When you pin a tab, it will display a pin icon and automatically moves towards the left side of the tab bar. All pinned tabs appear from left to right in the order you pinned. Hover over a pinned tab will show its execution time and the query. You can pin any number of results and quickly see what's pinned and what's not pinned. Simply click  to unpin a tab.

Query Explain

Query Explain provides detailed information about how a database query is executed by the database server. It helps you understand and optimize the performance of queries by analyzing the query execution plan.




When you click , Navicat sends an explain script to the database server. The server then generates an execution plan that outlines the steps it will take to execute the query and retrieve the requested data.

The **Explain** tab displays the execution plan. You can pin the tab by clicking .

You are allowed to explain selected portion of query, just simply highlight script in Query Editor and click .

Execution Plan - Visual (Available only in Navicat Premium, Enterprise and Standard Edition)

The diagram displays the operations performed by the query and the data passed between them. If the cost of an operation equals or exceeds the threshold value in the daigram, the number turns red. Click on an operation to view its statistical information. The information helps to understand what is happening internally when the query is executed.

Button / Option	Description
Cost Threshold(%)	Set the threshold value to determine when certain operations in the execution plan are considered important enough to be marked red.
	Zoom in or zoom out the diagram.
	Download the diagram as a PNG file.
	Filter the nodes in the diagram by the node type.
Find	Enter a search string to find matches.

Execution Plan - JSON

The text-based plan provides a complete set of information about the query execution displayed in JSON format. This format can be difficult to read and analyze, but is easy to share with others.

Execution Plan - Grid

The grid-based plan provides a complete set of information about the query execution.

Execution Plan - Statistic

Per Node Type - It shows the summary information of each node type in the visual graph.

Per Relation - It shows the statistical information that related to each collection.

Redis

Query Editor

Query Editor allows you to create and edit commands, prepare and execute selected queries. You can define multiple commands in one query window.

Navicat provides a wide range advanced features, such as compelling code editing capabilities, smart code-completion, command formatting, and more.

Command Formatting

To change the command format, simply choose from the **Format** menu -

Indent

Increase/decrease indent for the selected lines of codes.

Comment

Comment/uncomment the selected lines of codes.


Convert case

Format the selected codes into upper/lower case.

Code Completion


Code completion feature in Navicat pops up a list of suggestions as you type your command in the editor. It assists you with command completion and the available functions with their appropriate icons and information.

Code completion can be invoked by typing a character or pressing ESC.



When the suggestion list appears, press TAB to insert the first item. You can also select the needed item using UPPER ARROW or DOWN ARROW and then press TAB or ENTER.

If you select a snippet name from the list, the saved code will be inserted to the editor.



Hint: Resize the suggestion list by dragging the lower right corner.

You can enable or disable the code completion feature in [Settings](#).

Clipboard Stack

When you copy or cut some codes as usual in the editor, the copied content will also be added to Clipboard Stack. Clipboard Stack can store up to 10 items and use the last-in-first-out logic. To paste an item from Clipboard Stack, you can press COMMAND-SHIFT-V. Press COMMAND-SHIFT-V multiple times to cycle through Clipboard Stack.

Syntax Highlight

Navicat uses syntax highlighting which depending on the database associated with the query. Different databases have different sets of reserved keywords. You can configure the associated colors for different text fragments in [Settings](#).

Brace Highlight

Navicat supports to highlight the matching brace in the editor, i.e. () .

Note: The cursor must be on a brace to show the highlight.

```

1  ACL SETUSER john on >Jho!jjk >Tahc*mcx nocommands allkeys allchannels
2  ACL SETUSER temp on >Xtxsfaf3 nocommands allkeys allchannels
3  ACL SETUSER usr1 on clearselectors [(nocommands +@read)] (nocommands ~k1 ~k2 ~k3)
4  ACL SETUSER amy on ~* &* +@all >amy123

```

Find and Replace

Find

The Find bar is provided for quick searching for the text in the editor. Just simply choose **Edit -> Find -> Find** from the menu or press COMMAND-F, and then enter a search string.

Incremental searching is used here. As you type, the matched text is found and highlighted instantly. This saves your time from typing the entire text.

The search starts at the cursor's current position to the end of the file.

To find the previous or next occurrence, just simply click ◀ or ▶ .

Replace

To open the Replace bar, simply choose **Edit -> Find -> Find and Replace** from the menu bar or press OPTION-COMMAND-F. Then, enter the text you want to search and replace.

Click the **Replace** button to replace the first occurrence.

Click the **Replace All** button to replace all occurrences automatically.

There are some additional options for Find and Replace, click 🔍 :

Option	Description
Regular Expression	Search regular expressions.
Match Case	Enable case sensitive search.
Whole Words	Return the objects that match the entire word of the search string.

Copy with Quotes

To copy the command with quotes, just simply control-click the highlighted command. Then, select **Copy with Quotes** and choose the format.

Word Wrap

In the Word Wrap mode, the horizontal scrollbar is removed. Command that exceeds the width of the editor window size wraps to the next line. To enable Word Wrap, choose **View -> Word Wrap**.

Zoom In/Zoom Out

Navicat has the ability to zoom in or zoom out the command in the editor. The zooming options are available from the **View** menu. The same effect can be achieved with keyboard shortcuts.

Zoom In: [COMMAND-+]

Zoom Out: [COMMAND--]



Reset: [COMMAND-0]

Note: Editors that are opened in different tabs or windows will not be affected by the zoom.



Query Results

You can run the query in any servers. Select the target connection and database from the drop-down menu on the toolbar, and then click ▶ . If the query command is correct, the query executes and, if the query command is supposed to return data, the **Result** tab opens with the data returned by the query. If an error occurs while executing the query, execution stops, the appropriate error message is displayed.



Navicat displays query results in a user-friendly format. The **Result** tab displays the result data, returned by the query, as a grid. See [Data Viewer](#) for details.

Button	Description
	Activate the editor for viewing and editing data.
	Pin the tab.


Note: Navicat supports to return 20 result sets.


You are allowed to run selected portion of query, just simply highlight commands in the editor and click . To run the current command your cursor is on (position the cursor within the desired command), just simply click and hold the  button and select **Run Current Statement**.

Adjust Result Position

In Navicat, you have the flexibility to configure how query results are displayed. You can choose to show the query results on an entire page, on the right side of the editor, or at the bottom of the editor. This allows you to adapt the display layout based on your specific needs and preferences during data analysis and exploration in Navicat. To change the result position, use the  or  icon located in the upper right corner, or access the **View -> Result** menu.

Pin Query Result (Available only in Navicat Premium, Enterprise and Standard Edition)

Existing result tabs are removed when you re-execute the query. You can pin a result tab so that it remains visible after re-executing the query. Simply click  and its contents will not be cleared the next time you execute it.

When you pin a tab, it will display a pin icon and automatically moves towards the left side of the tab bar. All pinned tabs appear from left to right in the order you pinned. Hover over a pinned tab will show its execution time and the query. You can pin any number of results and quickly see what's pinned and what's not pinned. Simply click  to unpin a tab.

Custom Tab Name





To customize the names of the result tabs, simply add `// NAME:tab_name` before each command in the Query Editor.

```

1 // NAME:database
2 CONFIG GET databases
3
4 // NAME:user
5 ACL GETUSER user1
6
7 // NAME:data
8 SCAN 1050 COUNT 100


```

Message Summary database **user** data


Data Info    

#	Value
1	flags
2-1	on
2-2	nopass
2-3	sanitize-payload
3	passwords
4-1	(NULL)
5	commands
6	~@all
7	keys

Code Snippets

Code Snippets provide a easy way for you to insert reusable code into editor when writing statements or scripts. The Code Snippet pane is on the right side of the editor. If the editor window is docked to the Navicat main window, you can click the  icon in the Information pane to open the library.

The library includes built-in and user-defined snippets. Choose a label from the drop-down menu or enter a search string in the Search box to filter the list. If you want to show the available snippets according to your database type, you can control-click anywhere on the library and disable **Hide Snippets For Other Database Type**.




Built-in snippets are non-editable. A user-defined snippet can be edited by double-clicking it in the library and clicking **Edit**. If you want to hide the built-in snippets, you can control-click anywhere on the library and disable **Show Preset Snippets**.

Use Code Snippets

There are two ways to insert a snippet into the editor.

- You can start typing the name of a snippet in the editor. Smart code completion will pop up a list of suggestions for the word completion automatically. Select a snippet name from the list, the saved code will be inserted to the editor.



- You can simply drag and drop a snippet from the library into the editor.

After inserting the snippet with placeholders to the editor, you can easily navigate to them by clicking on one of the placeholders, and then using the TAB key and entering the information.


```

1 CASE case_value
2   WHEN when_value THEN
3     statement_list
4   ELSE
5     statement_list
6 END CASE;
7



```

Create Code Snippets

You can create your own code snippets and add them to the library. To create a code snippet, select your desired code in the editor, then control-click and select **Create Snippet**, or simply drag and drop the selected code to the Code Snippet pane.

Alternatively, click  in the Code Snippet pane. If you use this method, you must manually enter the code in the New Snippet window; code selected in the editor is not automatically added to the Code box.

Hint: Code snippets (.nsnippet) are stored under the default path, e.g. ~/Library/Application Support/PremiumSoft CyberTech/Navicat CC/Common/Snippet.

Option / Button	Description
Untitled text box	Enter the name of the snippet that displays in the library and the code completion list.
Database Type	Choose the database server type of the snippet.
Label	Choose an existing label or enter a new label name for the snippet.
Remarks	Enter a description for the snippet that displays in the library.
Code	Enter the code.
	Add a placeholder by highlighting any words in the code and click this button. The placeholder will be highlighted in light green.
	Remove a placeholder by highlighting it in the code and click this button.

Move / Copy Snippet To Project


If you have logged in to Navicat Cloud or On-Prem Server, you can synchronize the custom snippet in My Connections to a project.

- Control-click a snippet and select **Move Snippet To** or **Copy Snippet To**.
- Select an existing project.
- The snippet will be moved or copied to the project.

Hint: You can move / copy a snippet in a project to My Connections in a similar way.

Chapter 9 - Model (Available only in Navicat Premium and Enterprise Edition)

About Model

Model is a powerful tool for creating and manipulating database models. In the main window, click  **Model** to open the model object list.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB.

Some of key features are listed here:

- Create and manipulate conceptual/logical/physical models.
Note: Only Navicat Premium supports conceptual and logical models.
- Reverse engineer databases/schemas to a model.
- Forward engineer a physical model to a SQL/Script file or a database/schema.
- Compare two model workspaces.
- Generate data dictionaries from models.
- Create and edit table structures directly.

Hint: Workspace files (.nmodel) are saved under the default path, e.g. ~/Library/Application Support/PremiumSoft CyberTech/Navicat CC/Navicat Premium/Profiles. To open the folder, control-click a workspace file and select **Show in Finder**. If the workspace is synchronized to [Navicat Cloud](#) or [On-Prem Server](#), it will be stored in the cloud.

Open an external model file

1. In the menu bar, choose **File -> Open External File -> Model**.
2. Browse the file and click **Open** in the dialog window.

Save an opened external file as a Navicat workspace

1. In Workspace Designer, choose **File -> Save to Navicat**.
2. Enter the model name and choose the save location.
3. Click **OK**.


Save a Navicat workspace as an external file

1. In Workspace Designer, choose **File -> Save As External File**.
2. Choose the save path and enter the file name.

3. Click **Save**.

Workspace

A workspace is the place that comprises models, diagrams and data dictionaries. You can create multiple models, diagrams and data dictionaries in a workspace.



① Workspace Toolbar

The Workspace Toolbar provides controls that you can use to create models, diagrams and data dictionaries.

② Tab Bar

The Tab Bar allows you to switch among the opened items.

③ Content Pane

The Content pane shows all items in the workspace. To change the view, click the **Detail** or **Icon** button at the bottom of the window.

Detail View displays additional information about each item. You can sort items in Detail View, click the column header by which you want to sort the items.

Icon View displays your items as a grid of thumbnail images. You can filter the items by clicking a category (All, Data Source, Chart, Dashboard) in this view.

④ Properties Pane


The **General** tab shows the general information of the workspace or the selected item.

If the Properties pane is hidden, choose **View -> Show Properties** from the menu bar.

Model

About Model

A model is a collection of database objects that can be effectively utilized within diagrams. These objects can be reused across various diagrams, thereby increasing efficiency and consistency in the design and presentation of database structures.



1 Model Pane

The Model pane is the basic way to navigate with databases/schemas, tables, views, functions or entities.

2 Object Toolbar

The Object Toolbar provides controls that you can use to manipulate the object.

3 Object Pane

The Object pane shows the objects you created in the model.

4 Properties Pane

The **General** tab shows the general information of the selected object.

The **DDL** tab shows the DDL of the selected object.

If the Properties pane is hidden, choose **View -> Show Properties** from the menu bar.

Create Model

The essential steps to create a model are:

1. In the Workspace window, click .

2. Enter the name of the model and select a model type, target database, and database version.
3. Click **OK**.
4. A tab will open for you to edit the model.

Add Database / Schema

When creating a new model, a database (named default) is automatically created and it is the default database.

You can view all databases/schemas with their objects as tree structure on the Model pane.

To create a new database


1. On the Model pane, control-click the model name or database and select **New Database**.
2. Enter the name of the database.
3. Click **OK**.

To create a new schema

1. On the Model pane, control-click the database or schema and select **New Schema**.
2. Enter the name of the schema.
3. Click **OK**.


Create Table

The essential steps to create a table are:

1. On the Model tab, select Tables in the Model pane.
2. Click , or click and hold the down arrow and choose the table type.
3. Enter the name of the table.
4. Click **OK**.
5. A tab will open for you to edit the table.

Create View


The essential steps to create a view are:

1. On the Model tab, select Views in the Model pane.
2. Click .
3. Enter the name of the view.

4. Click **OK**.
5. A tab will open for you to edit the view.


Create Function / Procedure

The essential steps to create a function/procedure are:



1. On the Model tab, select Functions in the Model pane.
2. Click .
3. **Function Wizard** will pop up and it allows you to create a function/procedure easily.
4. Click **Finish**.
5. A tab will open for you to edit the function/procedure.

Create Collection


The essential steps to create a collection are:


1. On the Model tab, select Collections in the Model pane.
2. Click , or click and hold the down arrow and choose the table type.
3. Enter the name of the collection.
4. Click **OK**.
5. A tab will open for you to edit the collection.

Add Embedded Document


1. Click .
2. Enter the name of the field and select **object** data type.
3. Click the arrow icon left to the field name.
4. Click  and define the item.

Add Embedded Array of Documents

1. Click .
2. Enter the name of the field and select **object** data type.
3. Enable **Is Array**.
4. Click the arrow icon left to the field name.

5. Click  and define the item.


Add Predefined Object

1. Click .
2. Enter the name of the field and select **(Predefined Object)** data type.
3. Choose the predefined object.

Create Predefined Object


A predefined object refers to a specific document structure that is predefined or preconfigured. It is a predetermined schema or template that defines the fields and their data types within a MongoDB document. You can use predefined objects in any collection in the model to help maintain data integrity and establish consistent document structures.

The essential steps to create a predefined object are:

1. On the Model tab, select Predefined Object in the Model pane.
2. Click .
3. Enter the name of the predefined object.
4. Click **OK**.
5. A tab will open for you to edit the predefined object.

Create Entity

The essential steps to create an entity are:


1. On the Model tab, select Entities in the Model pane.
2. Click .
3. Enter the name of the entity.
4. Click **OK**.
5. A tab will open for you to edit the entity if your model is a logical model.

Diagram

About Diagram

A diagram is a visual representation of the relationships and structure of a data model. It depicts the tables, fields, collections, entities, attributes, and relationships between them in a clear and concise manner. You can use it in

database design and development processes to communicate and document the logical organization of data within your system.



1 Object Pane

The Object pane displays a list of all objects used in the diagram.


2 Toolbar

The Toolbar is located near the top of the diagram. The buttons display in the toolbar depend on the model type (physical, logical and conceptual) and server type. You can use the toolbar to perform some basic tasks, such as adding tables, views, functions, collections or entities, applying Auto Layout feature, etc.

3 Canvas

You can design your diagram on the Diagram Canvas. All added objects can be moved (by dragging them with mouse or by keyboard), resized, aligned to the grid, etc.

4 Properties Pane

The  **Properties** tab includes the basic layout settings, object settings and so on. The properties vary with the type of the object selected.

The  **DDL** tab shows the DDL of the selected object.

5 Overview Pane

The Overview pane displays the whole active diagram in the canvas. To zoom in or zoom out the selected area of the diagram, adjust the slider. Same effect can be achieved with keyboard shortcuts:


Zoom In: [COMMAND-Mousewheel Up]

Zoom out: [COMMAND-Mousewheel Down]

Reset Zoom: [COMMAND-0]

Create Diagram

The essential steps to create a diagram are:

1. In the Workspace window, click .
2. Enter the name of the diagram.
3. Click **OK**.
4. A tab will open for you to edit the diagram.

Properties


Once you have selected the diagram canvas, you can customize the diagram by changing its properties:

Option	Description
Diagram	
Default Model	Choose the default model of the diagram. All objects created in the diagram belong to the default model.
Diagram Notation	Choose the notation of the diagram.
Database Object Font	Set the font style of the database objects.
Black and white	Change the diagram color to black and white.
Show database object comments	Show object comments in the diagram.
Show table field comments	Show field comments in the diagram.
Show collection subfields	Show subfields in MongoDB collections.
Show database names	Show the database names of objects in the diagram.
Paper Size	Set the paper size of the canvas.
Pages	Set the Width and Height (pages) of the canvas.

Add Model Objects


If you have already created a model, you can add existing objects in the model to the diagram.

The essential steps to add a model object are:



1. In the Diagram tab, click .
2. Choose a model.
3. Double-click the object you want to insert into the diagram, or use the drag-and-drop method.

Add Tables

To add a new table

1. Click the  button from the toolbar.
2. Place it on the canvas.
3. Double-click the table to open the designer.

Hint: The new table will also add to the default model.

For Default diagram notation, the  icon means the field is a primary key. The  icon indicates that the field serves as an index.

The pop-up menu options of the table object in the canvas include:

Option	Description
Design Table	Edit the table structure in a table designer, e.g. fields, indexes, foreign keys, etc. The tabs and options in the designer depend on the diagram database type you are chosen.
Add Related Objects	Add all related objects to the selected table.
Add Field	Add a field at the end of the table.
Insert Field	Add a field above the selected field.
Delete Field	Delete the selected field.
Primary Key	Set the selected field as primary key.
Rename Field	Change the name of the selected field.
Cut	Remove the table from the diagram and put it on the clipboard.
Copy	Copy the table from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Save as Image	Save the table as a PNG file.
Select All Connected Objects	Select all objects in the diagram that are connected to the table.
Select All Tables	Select all tables in the diagram.
Delete from Diagram / Delete from Diagram and Model	Delete the table from the diagram or from both diagram and model.
Rename	Change the name of the table.
Color	Change the color of the table.
Size to Fit	Resize the table automatically to fit its contents.
Bring to Front	Bring the table to the foreground.
Send to Back	Move the table to the background.
Group / Ungroup	Group or ungroup the table and other objects in the diagram.
Lock / Unlock	Lock or unlock the table in the diagram.


Properties

Once you have selected the table, you can customize the table by changing its properties:



Option	Description
Table	
Table Name	Enter the name of the table.
Database Name	Enter the name of the database to which the table belongs.
Model Name	Show the name of the model to which the table belongs.
Position	Customize the position of the table.
Size	Customize the size of the table.
Style	Choose the style of the table. Auto - Auto-arrange the table into a compact or standard style when resizing. Standard - Show the table name and its fields. Compact - Show a table icon with its name below the icon.
Constrain proportions	Maintain the aspect ratio (the ratio of width to height) when resizing.
Color	Set the color of the table.
Bold	Make the table border bold.
Group / Ungroup	Group or ungroup the table and other objects in the diagram.
Lock / Unlock	Lock or unlock the table in the diagram.

Add Collections

To add a new collection

1. Click the  button from the toolbar.
2. Place it on the canvas.
3. Double-click the collection to open the designer.

Hint: The new collection will also add to the default model.

For Default diagram notation, the  icon means the field is a primary key. The  icon indicates that the field serves as an index.

The pop-up menu options of the collection object in the canvas include:

Option	Description
Design Collection	Edit the collection structure in a collection designer, e.g. fields, indexes, relations, etc.
Add Related Objects	Add all related objects to the selected collection.
Add Field	Add a field at the end of the collection.

Insert Field	Add a field above the selected field.
Delete Field	Delete the selected field.
Primary Key	Set the selected field as primary key.
Rename Field	Change the name of the selected field.
Cut	Remove the collection from the diagram and put it on the clipboard.
Copy	Copy the collection from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Save as Image	Save the collection as a PNG file.
Select All Connected Objects	Select all objects in the diagram that are connected to the collection.
Select All Collections	Select all collections in the diagram.
Delete from Diagram / Delete from Diagram and Model	Delete the collection from the diagram or from both diagram and model.
Rename	Change the name of the collection.
Color	Change the color of the collection.
Size to Fit	Resize the collection automatically to fit its contents.
Bring to Front	Bring the collection to the foreground.
Send to Back	Move the collection to the background.
Group / Ungroup	Group or ungroup the collection and other objects in the diagram.
Lock / Unlock	Lock or unlock the collection in the diagram.

Properties


Once you have selected the collection, you can customize the collection by changing its properties:

Option	Description
Collection	
Collection Name	Enter the name of the collection.
Database Name	Enter the name of the database to which the collection belongs.
Model Name	Show the name of the model to which the collection belongs.
Position	Customize the position of the collection.
Size	Customize the size of the collection.
Style	Choose the style of the collection. Auto - Auto-arrange the collection into a compact or standard style when resizing. Standard - Show the collection name and its fields. Compact - Show a collection icon with its name below the icon.
Constrain proportions	Maintain the aspect ratio (the ratio of width to height) when resizing.
Color	Set the color of the collection.
Bold	Make the collection border bold.
Group / Ungroup	Group or ungroup the collection and other objects in the diagram.

Lock / Unlock	Lock or unlock the collection in the diagram.
---------------	---

Add Foreign Keys

To add a foreign key

1. Click the  button from the toolbar.
2. Drag and drop the field of the child table/collection to the field of the parent table/collection.
OR
Drag and drop the child field to the empty space of the parent table/collection. The referenced field will be automatically created in the parent table/collection.
3. Double-click the foreign key connector to open the designer.

Hint: When you hover over a foreign key line, the referenced fields and the referencing fields are highlighted.

The pop-up menu options of the foreign key in the canvas include:

Option	Description
Design Foreign Key	Edit the foreign key in a table designer. The options in the designer depend on the diagram database type you are chosen.
Go to	Go to and select the connected table/collection.
Reroute Connectors	Reroute the connector to the closest points between two connected objects.
Copy	Copy the foreign key from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Save as Image	Save the foreign key as a PNG file.
Select All Connected Objects	Select all objects in the diagram that are connected by the foreign key.
Select All Relations	Select all foreign keys in the diagram.
Delete from Diagram and Model	Delete a foreign key from both diagram and model.
Color	Change the color of the foreign key.
Group / Ungroup	Group or ungroup the foreign key and other objects in the diagram.
Lock / Unlock	Lock or unlock the foreign key in the diagram.

Properties


Once you have selected the foreign key, you can customize the foreign key by changing its properties:

Option	Description
Foreign Key	
Name	Enter the name of the foreign key.
Position	Customize the position of the line.

Offset	Customize offset values for the start and end of the line.
Show name	Display the name of the foreign key.
Font	Set the font style of the name.
Bold	Apply a bold style to the name.
Italic	Apply an italic style to the name.
Color	Set the color of the line.
Line Width	Choose the thickness of the line.
Cardinality	Specify the relationship cardinality of the table/collection.
Visible	Show the connector.
Group / Ungroup	Group or ungroup the foreign key and other objects in the diagram.
Lock / Unlock	Lock or unlock the foreign key in the diagram.

Add Views

To add a new view

1. Click the  button from the toolbar.
2. Place it on the canvas.
3. Double-click the view to open the designer.

Hint: The new view will also add to the default model.

The pop-up menu options of the view object in the canvas include:

Option	Description
Design View	Edit the view structure in a view designer. The tabs and options in the designer depend on the diagram database type you are chosen.
Add Related Objects	Add all related objects to the selected view.
Cut	Remove the view from the diagram and put it on the clipboard.
Copy	Copy the view from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Save as Image	Save the view as a PNG file.
Select All Views	Select all views in the diagram.
Delete from Diagram / Delete from Diagram and Model	Delete the view from the diagram or from both diagram and model.
Rename	Change the name of the view.
Color	Change the color of the view.
Size to Fit	Resize the view automatically to fit its contents.
Bring to Front	Bring the view to the foreground.
Send to Back	Move the view to the background.

Group / Ungroup	Group or ungroup the view and other objects in the diagram.
Lock / Unlock	Lock or unlock the view in the diagram.

Properties

Once you have selected the view, you can customize the view by changing its properties:

Option	Description
View	
View Name	Enter the name of the view.
Database Name	Enter the name of the database to which the view belongs.
Model Name	Show the name of the model to which the view belongs.
Position	Customize the position of the view.
Size	Customize the size of the view.
Style	Choose the style of the view. Auto - Auto-arrange the view into a compact or standard style when resizing. Standard - Show the view name and its content. Compact - Show a view icon with its name below the icon.
Constrain proportions	Maintain the aspect ratio (the ratio of width to height) when resizing.
Color	Set the color of the view.
Bold	Make the view border bold.
Group / Ungroup	Group or ungroup the view and other objects in the diagram.
Lock / Unlock	Lock or unlock the view in the diagram.

Add Functions / Procedures

To add a new function/procedure

1. Click the f_x or P_x button from the toolbar.
2. Place it on the canvas.
3. Double-click the function/procedure to open the designer.

Hint: The new function/procedure will also add to the default model.

The pop-up menu options of the function/procedure object in the canvas include:

Option	Description
Design Function / Design Procedure	Edit the function/procedure structure in a function/procedure designer. The tabs and options in the designer depend on the diagram database type you are chosen.
Cut	Remove the function/procedure from the diagram and put it on the clipboard.

Copy	Copy the function/procedure from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Save as Image	Save the function/procedure as a PNG file.
Select All Functions	Select all functions/procedures in the diagram.
Delete from Diagram / Delete from Diagram and Model	Delete the function/procedure from the diagram or from both diagram and model.
Rename	Change the name of the function/procedure.
Color	Change the color of the function/procedure.
Size to Fit	Resize the function/procedure automatically to fit its contents.
Bring to Front	Bring the function/procedure to the foreground.
Send to Back	Move the function/procedure to the background.
Group / Ungroup	Group or ungroup the function/procedure and other objects in the diagram.
Lock / Unlock	Lock or unlock the function/procedure in the diagram.

Properties

Once you have selected the function/procedure, you can customize the function/procedure by changing its properties:

Option	Description
Function / Procedure	
Function Name / Procedure Name	Enter the name of the function/procedure.
Database Name	Enter the name of the database to which the function/procedure belongs.
Model Name	Show the name of the model to which the function/procedure belongs.
Position	Customize the position of the function/procedure.
Size	Customize the size of the function/procedure.
Style	Choose the style of the function/procedure. Auto - Auto-arrange the function/procedure into a compact or standard style when resizing. Standard - Show the function/procedure name and its content. Compact - Show a function/procedure icon with its name below the icon.
Constrain proportions	Maintain the aspect ratio (the ratio of width to height) when resizing.
Color	Set the color of the function/procedure.
Bold	Make the function/procedure border bold.
Group / Ungroup	Group or ungroup the function/procedure and other objects in the diagram.
Lock / Unlock	Lock or unlock the function/procedure in the diagram.



Add Entities

To add a new entity

1. Click the  button from the toolbar.

2. Place it on the canvas.
3. [Logical Model] Double-click the entity to open the designer.

Hint: The new entity will also add to the default model.

For Default diagram notation, the  icon means the attribute is a primary key. The  icon indicates that the attribute serves as an index.

The pop-up menu options of the entity object in the canvas include:

Option	Description
Design Entity	Edit the entity structure in an entity designer, e.g. attributes, indexes, relations, etc. Only for Logical Model.
Add Related Objects	Add all related objects to the selected entity.
Add Attribute	Add an attribute at the end of the entity.
Insert Attribute	Add an attribute above the selected attribute.
Delete Attribute	Delete the selected attribute.
Primary Key	Set the selected attribute as primary key.
Rename Attribute	Change the name of the selected attribute.
Cut	Remove the entity from the diagram and put it on the clipboard.
Copy	Copy the entity from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Save as Image	Save the entity as a PNG file.
Select All Connected Objects	Select all objects in the diagram that are connected to the entity.
Select All Entities	Select all entities in the diagram.
Delete from Diagram / Delete from Diagram and Model	Delete the entity from the diagram or from both diagram and model.
Rename	Change the name of the entity.
Color	Change the color of the entity.
Size to Fit	Resize the entity automatically to fit its contents.
Bring to Front	Bring the entity to the foreground.
Send to Back	Move the entity to the background.
Group / Ungroup	Group or ungroup the entity and other objects in the diagram.
Lock / Unlock	Lock or unlock the entity in the diagram.

Properties

Once you have selected the entity, you can customize the entity by changing its properties:


Option	Description
--------	-------------

Entity	
Entity Name	Enter the name of the entity.
Database Name	Enter the name of the database to which the entity belongs.
Model Name	Show the name of the model to which the entity belongs.
Position	Customize the position of the entity.
Size	Customize the size of the entity.
Style	Choose the style of the entity. Auto - Auto-arrange the entity into a compact or standard style when resizing. Standard - Show the entity name and/or its attributes. Compact - Show an entity icon with its name below the icon.
Constrain proportions	Maintain the aspect ratio (the ratio of width to height) when resizing.
Color	Set the color of the entity.
Bold	Make the entity border bold.
Group / Ungroup	Group or ungroup the entity and other objects in the diagram.
Lock / Unlock	Lock or unlock the entity in the diagram.

Add Labels

Labels are typically used to help document the diagram design process. For example, to explain a grouping table objects.

To add a new label

1. Click the  button from the toolbar.
2. Place it on the canvas.
3. Enter the caption.

The pop-up menu options of the label object in the canvas include:

Option	Description
Cut	Remove the label from the diagram and put it on the clipboard.
Copy	Copy the label from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Save as Image	Save the label as a PNG file.
Select All Labels	Select all labels in the diagram.
Delete from Diagram	Delete a label from the diagram.
Size to Fit	Resize the label automatically to fit its contents.
Bring to Front	Bring the label to the foreground.
Send to Back	Move the label to the background.
Group / Ungroup	Group or ungroup the label and other objects in the diagram.

Lock / Unlock	Lock or unlock the label in the diagram.
---------------	--

Properties


Once you have selected the label, you can customize the label by changing its properties:

Option	Description
Label	
Name	Enter the name of the label.
Position	Customize the position of the label.
Size	Customize the size of the label.
Constrain proportions	Maintain the aspect ratio (the ratio of width to height) when resizing.
Font	Set the font style of the label caption.
Bold	Apply a bold style to the label caption.
Italic	Apply an italic style to the label caption.
URL	Enter URL path to set the text as a hyperlink.
Group / Ungroup	Group or ungroup the label and other objects in the diagram.
Lock / Unlock	Lock or unlock the label in the diagram.

Add Notes

Notes are typically used to help document the diagram design process. For example, to explain a grouping table objects.

To add a new note

1. Click the  button from the toolbar.
2. Place it on the canvas.
3. Enter the content.

The pop-up menu options of the note object in the canvas include:

Option	Description
Cut	Remove the note from the diagram and put it on the clipboard.
Copy	Copy the note from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Save as Image	Save the note as a PNG file.
Select All Notes	Select all notes in the diagram.
Delete from Diagram	Delete a note from the diagram.
Color	Change the color of the note.
Size to Fit	Resize the note automatically to fit its contents.
Bring to Front	Bring the note to the foreground.

Send to Back	Move the note to the background.
Group / Ungroup	Group or ungroup the note and other objects in the diagram.
Lock / Unlock	Lock or unlock the note in the diagram.

Properties


Once you have selected the note, you can customize the note by changing its properties:

Option	Description
Note	
Name	Enter the name of the note.
Position	Customize the position of the note.
Size	Customize the size of the note.
Constrain proportions	Maintain the aspect ratio (the ratio of width to height) when resizing.
Font	Set the font style of the note content.
Bold	Apply a bold style to the note content.
Italic	Apply an italic style to the note content.
Color	Set the color of the note.
Group / Ungroup	Group or ungroup the note and other objects in the diagram.
Lock / Unlock	Lock or unlock the note in the diagram.

Add Images

You can insert images (BMP, JPG, JPEG or PNG files) to your diagram for design or identification purposes.

To add a new image

1. Click the  button from the toolbar.
2. Place it on the canvas.
3. Select an image file in the Open dialog box.

Hint: You can simply add an image from the clipboard by pressing COMMAND-V.

The pop-up menu options of the image object in the canvas include:

Option	Description
Cut	Remove the image the diagram and put it on the clipboard.
Copy	Copy the image from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Save as Image	Save the image as a PNG file.
Select All Images	Select all images in the diagram.
Delete from Diagram	Delete an image from the diagram.

Bring to Front	Bring the image to the foreground.
Send to Back	Move the image to the background.
Group / Ungroup	Group or ungroup the image and other objects in the diagram.
Lock / Unlock	Lock or unlock the image in the diagram.

Properties


Once you have selected the image, you can customize the image by changing its properties:

Option	Description
Image	
Name	Enter the name of the image.
Opacity	Set the opacity of the image.
Position	Customize the position of the image.
Size	Customize the size of the image.
Original Size	Reset the image to its original size.
Constrain proportions	Maintain the aspect ratio (the ratio of width to height) when resizing.
URL	Enter URL path to set the image as a hyperlink.
Group / Ungroup	Group or ungroup the image and other objects in the diagram.
Lock / Unlock	Lock or unlock the image in the diagram.

Add Shapes

Navicat includes some pre-defined shapes for creating database model diagrams: line, arrow, curve, connector, rectangle, ellipse, user, database, cloud, trigger, server, desktop, laptop, mobile, man, woman.

To add a new shape

1. Click the  button from the toolbar.
2. Select a shape.
3. Place it on the canvas.

To connect objects with a connector

1. Drag one endpoint of the connector to an object until it snaps to the object (a blue outline appears around the object).
2. Drag the other endpoint until the connector snaps to another object.

Hint: Lines, arrows and curves can act as connectors. You can enable the **As connector** option in the Properties pane.

The pop-up menu options of the shape object in the canvas include:

Option	Description
Common	
Cut	Remove the shape from the diagram and put it on the clipboard.
Copy	Copy the shape from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Save as Image	Save the shape as a PNG file.
Select All Shapes	Select all shapes in the diagram.
Delete from Diagram	Delete a shape from the diagram.
Color	Change the color of the shape.
Bring to Front	Bring the shape to the foreground.
Send to Back	Move the shape to the background.
Group / Ungroup	Group or ungroup the shape and other objects in the diagram.
Lock / Unlock	Lock or unlock the shape in the diagram.
Line, Arrow and Curve	
Add Vertex	Add a vertex at the mouse cursor position.
Delete Vertex	Delete a vertex at the mouse cursor position.
Delete All Vertices	Delete all vertices on the selected line.
Go to	Go to and select the connected object.
Connector	
Go to	Go to and select the connected object.
Reroute Connectors	Reroute the connector to the closest points between two connected objects.

Properties

Once you have selected the shape, you can customize the shape by changing its properties:


Option	Description
Common	
Name	Enter the name of the shape.
Position	Customize the position of the shape.
Show name	Display the name label of the shape.
Name Position	Change the label position.
Font	Set the font style of the name.
Bold	Apply a bold style to the name.
Italic	Apply an italic style to the name.
Color	Set the color of the shape.
Group / Ungroup	Group or ungroup the shape and other objects in the diagram.
Lock / Unlock	Lock or unlock the shape in the diagram.
Line, Arrow, Curve and Connector	
Offset	Customize offset values for the start and end of the line.
Line Width	Choose the thickness of the line.
Cap Style	Choose the cap style of the line.

Dash Style	Choose the dash style of the line.
Join Style	Choose the join style of the line.
Begin Style	Choose the style of the line's back.
End Style	Choose the style of the line's front.
As connector	Allow you to connect objects.
Rectangle, Ellipse, User, Database, Cloud, Trigger, Server, Desktop, Laptop, Mobile, Man and Woman	
Size	Customize the size of the shape.
Constrain proportions	Maintain the aspect ratio (the ratio of width to height) when resizing.
Border Color	Change the color of the shape's border.
Border Width	Choose the thickness of the border.
Shape Style	Change the style of the shape.

Add Layers

Layers are used to help organize objects (e.g. tables, notes, images, etc) on the canvas. You can add all related objects to the same layer. For example, you may choose to add all your sales related tables to one layer.

To add a new layer

1. Click the  button from the toolbar.
2. Place it on the canvas.
3. Move objects into the layer and select **Add To Layer**.

The pop-up menu options of the layer object in the canvas include:

Option	Description
Cut	Remove the layer from the diagram and put it on the clipboard.
Copy	Copy the layer from the diagram to the clipboard.
Paste	Paste the content from the clipboard into the diagram.
Save as Image	Save the layer as a PNG file.
Select All Layers	Select all layers in the diagram.
Delete from Diagram	Delete a layer from the diagram.
Color	Change the color of the layer.
Size to Fit	Resize the layer automatically to fit its contents.
Bring to Front	Bring the layer to the foreground.
Send to Back	Move the layer to the background.
Group / Ungroup	Group or ungroup the layer and other objects in the diagram.
Lock / Unlock	Lock or unlock the layer in the diagram.

Properties

Once you have selected the layer, you can customize the layer by changing its properties:

Option	Description
Layer	
Name	Enter the name of the layer.
Position	Customize the position of the layer.
Size	Customize the size of the layer.
Constrain proportions	Maintain the aspect ratio (the ratio of width to height) when resizing.
Font	Set the font style of the title.
Title Position	Change the title position.
Color	Set the color of the layer.
Group / Ungroup	Group or ungroup the layer and other objects in the diagram.
Lock / Unlock	Lock or unlock the layer in the diagram.

Work with Diagram Canvas

Show Grid

To turn the grid on in the diagram canvas, choose **View -> Show Grid** from the menu bar.

Show Page Border

To turn the page border on in the diagram canvas, choose **View -> Show Page Border** from the menu bar.

Snap to Grid

To align objects on the canvas with the grid, choose **View -> Snap To Grid** from the menu bar.

Align Multiple Objects

1. Select the objects you want to align.
2. Control-click the selected objects, and then select one of these commands from the **Alignment** menu:

Option	Description
Align Left	Align objects along their left edges.
Align Center	Align objects vertically through their centers.
Align Right	Align objects along their right edges.
Align Top	Align objects along their top edges.
Align Middle	Align objects horizontally through their middles.
Align Bottom	Align objects along their bottom edges.

Arrange Objects Equidistant

1. Select at least three objects.


- Control-click the selected objects, and then select one of these commands from the **Distribute** menu:

Option	Description
Horizontally	Arrange the objects horizontally.
Vertically	Arrange the objects vertically.


Apply Auto Layout

Navicat provides a layout facility for arranging objects on diagrams. Your diagram is reorganized following the specific settings you define. Objects do not overlap and connectors do not cross over one another.


Apply Auto Layout to Entire Diagram

- Click on the canvas.
- Click .

Apply Auto Layout to Selected Objects

- Select the objects you want to apply auto layout.
- Click .

Apply Auto Layout to All Objects in Layer


- Select the layer.
- Click .

Change Auto Layout Settings

To change the Auto Layout format settings, simply choose **View** -> **Auto Layout With** from the menu and set the following options:

Option	Description
Object Distance	The distance between the objects in the diagram.
Quality	The quality of the auto layout output.
Auto diagram dimension	Choose the suitable diagram dimension automatically.
Auto size tables to fit	Resize the table to fit its content automatically.

Preview Diagram

You can preview the diagram using the whole screen. The title bar, toolbar, tab bar, Objects pane and Properties pane will be hidden while in this mode. To preview a diagram, click .

To exit the preview mode, press the ESC key and the workspace window will be returned to its previous state.

Print & Export Diagram

Print Diagram

You can print the current diagram to the printer.

1. Choose **File** -> **Print**.
2. Select your print options.
3. Click **OK**.

Export Diagram to File

You can export the current diagram to various types of images and files: PDF, PNG, SVG or JPG.

1. Choose **File** -> **Export To** and choose the file format.
2. Choose the path and enter the file name.
3. Click **Save**.



Data Dictionary

About Data Dictionary

Data Dictionary serves as a reference for understanding and documenting the structure and semantics of the data model. It provides a comprehensive description of the structure, relationships, and constraints of the objects in the model.

Create Data Dictionary

The essential steps to create a data dictionary are:

1. In the Workspace window, click .
2. Enter the name of the data dictionary.
3. Click **OK**.
4. A tab will open for you to edit the data dictionary.
5. Click .

Reverse Engineering

About Reverse Engineering

Reverse Engineering is the process of creating a data model from a database/schema. Navicat allows you to load existing database structures to create new models, or synchronize database differences to an existing model.

Synchronize Database to Model

The **Synchronize Database to Model** feature allows you to compare a database or schema with an existing model, states the differences between their structures, and offers synchronizing modifications in the database or schema into the model.

Navicat provides a step-by-step wizard for you to complete the task:

1. In the Workspace window, choose **Tools -> Reverse Engineering -> Synchronize Database to Model**.
2. Select the source connection, database, schema, and select the target model, database, schema.
3. Click **Options** and select the compare / advanced options.
4. Click **Compare** to show the differences between source and target objects.
5. Select the objects you want to synchronize.
6. Click **Next** to execute the process.

Choose Connections

The first step is to define the source connection and the target model.

Choose Comparing Options

Then, click the **Options** button to select the compare / advanced options for the synchronization process.

Note: The following options depend on the diagram database type you are chosen and sort in ascending order.

Option	Description
Compare auto increment value	Compare the auto increment values of tables.
Compare character set	Compare the character sets of tables.
Compare checks	Compare check constraints.
Compare collation	Compare the collations of tables.
Compare definers	Compare the definers of views.
Compare excludes	Compare exclusion constraints.
Compare foreign keys	Compare the foreign keys of tables.
Compare functions	Compare function and procedure objects.

Compare identity last value	Compare the identity last values of tables.
Compare indexes	Compare table indexes.
Compare owners	Compare the owners of database objects.
Compare partitions	Compare table partitions.
Compare primary keys	Compare the primary keys of tables.
Compare rules	Compare rule objects.
Compare sequences	Compare sequence objects.
Compare sequence last values	Compare the last values of sequences.
Compare storage	Compare table storages.
Compare table options	Compare other table options.
Compare tables	Compare table objects.
Compare triggers	Compare table triggers.
Compare uniques	Compare unique constraints.
Compare views	Compare view objects.
Drop with CASCADE	Drop the dependent database objects with the CASCADE option.
Identifier Case Sensitivity	Ignore or consider the case of identifiers when mapping, or use the server default setting.

Start Comparison

Click the **Compare** button to compare the source database and the target model.

View Comparison Results

After comparing structures, the tree view shows the differences between the source and target databases or schemas. Check the objects you want to apply to the target. You can expand the objects to view the detailed structure.

The screenshot shows a comparison tool interface. At the top, it indicates the source is 'MySQL sakila3' and the target is 'Model_2 default'. Below this, there's a table with columns 'Source Object', 'Operation', and 'Target Object'. The 'category' object is selected and expanded, showing a list of columns with checkboxes and operation symbols (green plus for additions, red X for deletions). Below the table, there are two panels: 'DDL Comparison' and 'Deployment Script', both showing the SQL DDL for the 'category' table in the source and target respectively.

You can choose to group the objects in the tree views by object types or operations by selecting **Group by Object Type** or **Group by Operation**.

Operation	Description
→	Object exists in both source and target databases/schemas, but they have different definition. The target object will be modified based on the source object.
+	Object does not exist in the target database/schema. It will be created in the target.
×	Object does not exist in the source database/schema. The target object will be deleted.
=	Object exists in both source and target databases/schemas and they have identical definition. No operation will be applied.

When you selected an object in the tree view, the **DDL Comparison** tab shows the DDL statements/scripts of that object in the source and the target, and the **Deployment Script** tab shows the detailed statements/scripts of the object that will be updated in the target model.

Click the **Next** button to execute the process. The window will display the execution progress, execution time, and success or failure messages.

Reverse Database to Model

The **Reverse Database to Model** feature allows you to create a database model from an existing database or schema.

Navicat provides a step-by-step wizard for you to complete the task:

1. In the Workspace window, choose **Tools -> Reverse Engineering -> Reverse Database to Model**.
2. Select the source connection, database, schema, and select the target model, database, schema. Choose **New Model** and the model type if you want to create a new model.
3. Click **New**.
4. Select the objects you want to import.
5. Enable **Import To Diagram** and select a diagram if you want to add the objects to a diagram. Choose **New Diagram** if you want to import objects to a new diagram.
6. Click **Start**.

You can also simply create a new model diagram using reverse engineering in the Navicat main window. For example, control-click an opened database and select **Reverse Database to Model**.

Forward Engineering

About Forward Engineering

Forward engineering is the process of generating the physical database schema from a physical model. Navicat allows you to synchronize model differences to an existing database, or export models to .sql or .script files.

Synchronize Model to Database

The **Synchronize Model to Database** feature allows you to compare a model with an existing database or schema, states the differences between their structures, and offers synchronizing the structures in model to the target connection.

Navicat provides a step-by-step wizard for you to complete the task:

1. In the Workspace window, choose **Tools -> Forward Engineering -> Synchronize Model to Database**.
2. Select the source model, database, schema, and select the target connection, database, schema.
3. Click **Options** and select the compare / advanced options.
4. Click **Compare** to show the differences between source and target objects.
5. Select the objects you want to synchronize.
6. Click **Next** to generate a set of scripts.
7. Click **Start**.

Choose Connections

The first step is to define the source model and the target connection.

Choose Comparing Options

Then, click the **Options** button to select the compare / advanced options for the synchronization process.

Note: The following options depend on the diagram database type you are chosen and sort in ascending order.

Option	Description
Compare auto increment value	Compare the auto increment values of tables.
Compare character set	Compare the character sets of tables.
Compare checks	Compare check constraints.
Compare collation	Compare the collations of tables.
Compare definers	Compare the definers of views.
Compare excludes	Compare exclusion constraints.
Compare foreign keys	Compare the foreign keys of tables.
Compare functions	Compare function and procedure objects.
Compare identity last value	Compare the identity last values of tables.
Compare indexes	Compare table indexes.
Compare owners	Compare the owners of database objects.
Compare partitions	Compare table partitions.

Compare primary keys	Compare the primary keys of tables.
Compare rules	Compare rule objects.
Compare sequences	Compare sequence objects.
Compare sequence last values	Compare the last values of sequences.
Compare storage	Compare table storages.
Compare table options	Compare other table options.
Compare tables	Compare table objects.
Compare triggers	Compare table triggers.
Compare uniques	Compare unique constraints.
Compare views	Compare view objects.
Drop with CASCADE	Drop the dependent database objects with the CASCADE option.
Identifier Case Sensitivity	Ignore or consider the case of identifiers when mapping, or use the server default setting.

Start Comparison

Click the **Compare** button to compare the source model and the target database.

View Comparison Results

After comparing structures, the tree view shows the differences between the source and target databases or schemas. Check the objects you want to apply to the target. You can expand the objects to view the detailed structure.

The screenshot shows a comparison tool interface with the following components:

- Group by Operation**: A dropdown menu at the top left.
- Model - MySQL sakila**: The source database being compared.
- MySQL sakila3**: The target database being compared.
- Source Object**: A tree view showing objects like 'actor', 'category', and 'film_category'. The 'category' object is expanded, showing fields like 'category_id', 'name', and 'last_update', along with constraints like '(Primary Key)' and '(Table Options)'.
- Operation**: A column showing the type of change required, such as a right-pointing arrow (→) for modifications or a plus sign (+) for additions.
- Target Object**: A tree view showing the corresponding objects in the target database, including 'Quater', 'Type', and 'Amount' which are not in the source.
- DDL Comparison**: A button to view the DDL for the selected object.
- Deployment Script**: A text area showing the SQL DDL for the 'category' table in both source and target, highlighting differences in field definitions and constraints.

You can choose to group the objects in the tree views by object types or operations by selecting **Group by Object Type** or **Group by Operation**.

Operation	Description
→	Object exists in both source and target databases/schemas, but they have different definition. The target object will be modified based on the source object.

+	Object does not exist in the target database/schema. It will be created in the target.
×	Object does not exist in the source database/schema. The target object will be deleted.
=	Object exists in both source and target databases/schemas and they have identical definition. No operation will be applied.

When you selected an object in the tree view, the **DDL Comparison** tab shows the DDL statements/scripts of that object in the source and the target, and the **Deployment Script** tab shows the detailed statements/scripts of the object that will be executed in the target databases.

Click the **Next** button to show the scripts of all selected objects.

Edit & Execute Selected Scripts

You can view all scripts that will be executed in the target database in the **Deployment Script** tab.

Deployment Options Button	Description
Deployment Options	Continue on error - Ignore errors that are encountered during the execution process if necessary. Include deployment query in message log - Show the deployment queries in the Message Log tab during execution.
Edit Script	Open the Edit Deployment Script window to rearrange the order of the scripts.
Copy Script to Clipboard	Copy all scripts from the Deployment Script tab to the clipboard.
Open Script in Query Editor	Open a new query window and display the scripts.

In the **Edit Deployment Script** window, use the arrow buttons to move the scripts.

Then, click the **Start** button to execute the scripts. The window will display the execution progress, execution time, and success or failure messages.

Export Model to SQL/Script File

After finishing your model, you can save structures and relations from the model into a sql or script file.

Navicat provides a step-by-step wizard for you to complete the task:

1. In the Workspace window, choose **Tools -> Forward Engineering -> Export Model to SQL/Script File**.
2. Enter the file information and select the objects.
3. Click **OK**.

General Properties

Option	Description
File	Set the location path of the output file.

Model	Choose the model you wish to export.
Schema	Choose the schema you wish to export.
Objects	Choose objects in the model you wish to export.

Advanced Properties

Note: The following options depend on the diagram database type you are chosen and sort in ascending order.

Option	Description
Include auto increment	Include the auto increment values of tables.
Include character set	Include table and field character sets.
Include checks	Include check constraints.
Include collation	Include the collations of tables.
Include Drop SQL	Include drop object SQL statements.
Include Drop With CASCADE	Include drop object SQL statements with the CASCADE option.
Include excludes	Include exclusion constraints.
Include foreign keys	Include the foreign keys of tables.
Include indexes	Include table indexes.
Include primary keys	Include the primary keys of tables.
Include rules	Include rule objects.
Include schema	Qualify object names with the schema name. Otherwise, only object names are included in SQL statements.
Include triggers	Include table triggers.
Include uniques	Include unique constraints.
Server Version	Select the server version for the file.

Compare Model Workspace

Compare Model Workspace is a powerful tool that allows you to compare two model workspaces, view and resolve differences between them.

Navicat provides a step-by-step wizard for you to complete the task:

1. In the Workspace window, choose **Tools -> Compare Models Workspace**.
2. Select the workspace you want to sync with the current workspace.
3. Click **Compare** to show the differences between source and target objects.
4. Select the objects you want to synchronize.
5. Click **Apply Changes** to view the number of changes.

6. Click **Apply**.

Choose Source Workspace

The first step is to define the source workspace. You can choose an existing workspace in Navicat or an external workspace file.

Then, click the **Compare** button.

View Comparison Results

After comparing, the tree view shows the differences between the source and target workspaces. Check the objects you want to apply to the target. You can expand the objects to view the detailed structure.

Choose an option from the drop-down list to show the objects.

Option	Description
All Objects	Show all objects in the source and target.
Objects with Difference	Show all objects that are different in the source and target.
Objects To Be Added	Only show the objects that do not exist in the target.
Objects To Be Updated	Only show the objects that exist in both source and target, but they have different structures.
Objects To Be Deleted	Only show the objects that do not exist in the source.

When you selected an object in the tree view, the **DDL Comparison** tab shows the DDL statements/scripts of that object in the source and the target, and the **Reference Script** tab shows the detailed statements/scripts of the object that will be executed in the target database.

Apply Changes

Click the **Apply Changes** button to apply changes to the selected objects.

Model Conversion

Navicat allows you to convert your models from one database type to another database type, e.g. MariaDB 10.0 physical model to PostgreSQL 9.0 physical model. With Navicat Premium, you can also convert your models from one model type to another model type, e.g. physical model to logical model.

Convert a model

1. In the Workspace tab, control-click a model and select **Model Conversion Wizard**.
2. Select the target workspace.
3. Enter the model name.
4. Choose the model type.

5. Choose the target database and version if necessary.
6. If you want to convert all related diagrams, enable **Convert with related Diagram**.
7. Click **Start**.
8. A tab will open for you to edit the model.

Conversion Behaviour

- All data types are converted automatically.
- When converting from one database type to another, the conversion process does not change the syntax of views, functions, and procedures.
- When converting a physical model to a logical/conceptual model, all views are converted to entities, and all functions and procedures are removed.
- If the target database version is MySQL 4.0 or below, all views are removed.
- If the source database type is MongoDB, all views, functions, and procedures are removed.
- If the target database type is MongoDB, all views, functions, and procedures are removed.
- If the target database type is SQLite, all functions and procedures are removed.

Model Hints and Tips

Navicat provides some useful hints to work on the diagram more effectively.

Locate Object in Diagram Canvas

Double-click an object in the left pane will jump to the corresponding object on the canvas.

Delete Object from Model

Select an object on the canvas and press SHIFT+DELETE.

Open Object Designer

Double-click an object in the left pane or the canvas.

Get Object Statement

Select and copy an object on the canvas, and paste it to other text editors.

Add / Edit Field without Object Designer

Select an object and click the object name on the canvas, and then press DOWN ARROW to add/edit fields. Navicat will predict field types according to field names you entered.

INTEGER/int/int4/NUMBER

- suffix "id", "no" (if it is the first column, it will be predicted as a primary key)
- suffix "num"
- "qty", "number"
- exactly "age", "count"

DECIMAL(10,2)/decimal(10,2)/NUMBER/REAL/money

- suffix "price", "cost", "salary"

FLOAT/double/float8/NUMBER/REAL/float

- "size", "height", "width", "length", "weight", "speed", "distance"

DATE/datetime/date/TEXT/datetime2

- "date", "time"

VARCHAR(255)/varchar(255)/VARCHAR2(255)/TEXT

- other field names


Enter * before the field name to recognize as primary key. e.g. *itemNo:int.

Enter : between field name and field type to custom field type, e.g. itemName:varchar(255).

Reorder Field

Select an object on the canvas, then press and hold the SHIFT key. Use  to drag the field to a desired location.

Delete Field

Select an object on the canvas, then press and hold the SHIFT key. Use  to drag the desired field out of the object.

Add Vertex to Line / Arrow / Curve

Select a line, arrow or curve on the canvas. Press and hold the SHIFT key and click on it to add vertex.

Delete Vertex on Line / Arrow / Curve

Select a line, arrow or curve on the canvas. Press and hold the SHIFT key and click on the vertex.

View Object's Model and Database

Press and hold the SPACE key.

Switch to Hand Mode


Press and hold the SPACE key, then move the diagram.

Chapter 10 - Debugger (Available only in Navicat Premium, Enterprise and Standard Edition)







About Debugger


Navicat provides two code debuggers: **Oracle PL/SQL Debugger** and **PostgreSQL PL/pgSQL Debugger**. With the debuggers, you can toggle breakpoints, fetch call stacks, view variable values, trace the code, etc.

Oracle PL/SQL Debugger

Oracle PL/SQL Debugger provides step-by-step code debugging for functions, procedures, packages and queries. To launch the debugger, click the  button in the designer of the mentioned objects.

You can perform the most commonly used actions for debugging on the toolbar or menu:

Button	Description
	Start running code in debug mode. Enter the Input Parameters if necessary. The debugger executes your code until the end of the code or the next breakpoint is reached.
	Stop stepping the code. The execution will stop and cannot resume it.
	Resume the execution. The current line will be executed. If the line is a procedure or function call, it will bypass the procedure or function. The counter will then move to the next line of code.
	Resume the execution. The current line will be executed. If the line is a procedure or function call, the counter goes to the first statement in the procedure or function. Otherwise, the counter will move to the next line of code.
	Resume the execution. The remaining part of the code within the current procedure or function will be executed. Subsequently, the counter will jump to the line which is just after the caller of the procedure or function.
	Resume the execution. The counter will jump to the last line of the procedure or function.

The **Code** pane shows the code of the procedure or function. You can add/remove breakpoints for debugging by clicking  in the grey area beside each statement.

The **Breakpoints** pane displays all the breakpoints.

The **Call Stack** pane displays a list of procedures and functions as they are called. To jump to a procedure or function, control-click it and select **Jump To**.


The **Local Variables** pane displays all local variables and their values. To add a variable to the watch list, control-click it and select **Add to Watch List**.

The **Parameters** pane displays the inputted parameters. To add a parameter to the watch list, control-click it and select **Add to Watch List**.






The **Watch List** pane displays information about the variables being watched, allowing you to delete or edit watch variables. To edit the value of a watch variable, control-click a variable and select **Set Value**. To delete a watch variable, control-click a variable and select **Remove Variable**.


The **Log** pane displays the message log when debugging the code and the results after the procedure or function has completed the execution.

PostgreSQL PL/pgSQL Debugger

PostgreSQL PL/pgSQL Debugger provides step-by-step code debugging for PL/pgSQL procedures/functions. To launch the debugger, click the  button in the function designer.

You can perform the most commonly used actions for debugging on the toolbar or menu:

Button	Description
	Start running code in debug mode. Enter the Input Parameters if necessary. The debugger executes your code until the end of the code or the next breakpoint is reached. Keyboard shortcut: F9
	Stop stepping the code. The execution will stop and cannot resume it.
	Resume the execution. The current line will be executed. If the line is a procedure or function call, it will bypass the procedure or function. The counter will then move to the next line of code. Keyboard shortcut: F10
	Resume the execution. The current line will be executed. If the line is a procedure or function call, the counter goes to the first statement in the procedure or function. Otherwise, the counter will move to the next line of code. Keyboard shortcut: F11
	Resume the execution. The remaining part of the code within the current procedure or function will be executed. Subsequently, the counter will jump to the line which is just after the caller of the procedure or function. Keyboard shortcut: COMMAND-F11

The **Code** pane shows the code of the procedure or function. You can add/remove breakpoints for debugging by clicking  in the grey area beside each statement.

The **Breakpoints** pane displays all the breakpoints.

The **Call Stack** pane displays a list of procedures or functions as they are called. To jump to a procedure or function, control-click it and select **Jump To**.

The **Local Variables** pane displays all local variables and their values. To add a variable to the watch list, control-click it and select **Add to Watch List**.


The **Parameters** pane displays the inputted parameters. To add a parameter to the watch list, control-click it and select **Add to Watch List**.

The **Watch List** pane displays information about the variables being watched, allowing you to delete or edit watch variables. To edit the value of a watch variable, control-click a variable and select **Set Value**. To delete a watch variable, control-click a variable and select **Remove Variable**.

The **Log** pane displays the message log when debugging the code and the results after the procedure or function has completed the execution.

Chapter 11 - Pub/Sub (Available only in Navicat Premium, Enterprise and Standard Edition)

About Pub/Sub

Pub/Sub is Publish and Subscribe, allows users to subscribe to channels and receive messages when messages are published to those channels. Users can listen to one or more channels and react to the messages as they come in. In the main window, click  **Pub/Sub** to open the Pub/Sub object list.


Note: Available only for Redis.

You can save the channels you are currently subscribed to as a profile to quickly resume subscriptions when you open the profile.

Hint: Profiles (.npsbredis) are stored under the [Settings Location](#).





Pub/Sub Window





The Pub/Sub Window consists of a toolbar, Channels pane and Messages pane.



1 Toolbar

The toolbar of Pub/Sub provides the following functions:

Button	Description
	Subscribe to channels, patterns or shard channels.
	Unsubscribe the selected channels.
	Unsubscribe all channels temporarily.
	Resume all channels.

	Toggle a pane for posting a message to a channel.
	Create an archive file for the current messages.
	Mute the channels. All new messages will not be received.
	Clear all messages on the Messages pane.

② Channels Pane

The Channels pane shows all subscribed channels.

③ Messages Pane

The Messages pane shows all messages in the subscribed channels. You can show/hide the messages in different states by control-clicking the grid.

Message texts in different colors indicate:

- Black - Messages sent to a channel
- Grey - System messages
- Blue - Publish / Received messages
- Red - Error messages


④ Message Details Pane

The Message Details pane shows the detailed information of the selected message.


Subscribe Channels

Channels exist on the system only when a subscriber is listening to messages on it, so there is no need to ever create or delete channels.

Subscribe a channel

1. Click .
2. You can find out which channels are active on your Redis server. If no active channels, you can customize one.
3. Click **Subscribe**.
4. The subscribed channel appears on the Channels pane.


Publish a message to a channel

1. Click .
2. Choose a channel type and a channel.
3. Enter the message.

4. Click **Publish**.


Hint: You can control-click a channel on the Channels pane and select **Publish To** to post messages to that channel.

Archive messages


1. Click .
2. Enter the file name.
3. Click **Save**.

Hint: Archived files (.nrpsbmlog) are stored under the [Settings Location](#). To open the folder, control-click an archived file in the Objects tab and select **Show in Finder**.

Hide server messages from a channel

1. Click  next to the channel name.


Unsubscribe a channel

1. Select a channel on the Channels pane.
2. Click .

Channel Colorings


You can highlight channels by colors for identifying channels and their messages. It lets you instantly know which channel a message is from. The highlighted color displays in the Channels pane and the Messages pane.

To highlight a channel, control-click a channel on the Channels pane and select **Color**.



Chapter 12 - Aggregation Pipeline (Available only in Navicat Premium, Enterprise and Standard Edition)

About Aggregation Pipeline

Aggregation Pipeline is a specific flow of operations that processes and transforms data, performs complex calculations, and generates aggregated results. Navicat provides the ability to create aggregation pipelines in a simple and instant way. In the main window, click  **Pipeline** to open the aggregation pipeline object list.







You can save your settings as a profile for future use or setting [automation tasks](#).

Hint: Aggregation Pipeline (.nagg) are stored under the [Settings Location](#).

Note: Available only for MongoDB.


Aggregation Pipeline Designer

Aggregation Pipeline Designer is the basic Navicat tool for working with aggregation pipelines.

Button	Description
	Import a script file to build the pipeline.
	Preview All - Preview the output. Preview All with Reload - Reload the sampled documents and preview the output.
	Execute the pipeline.
	Show the execution plan.
	Stop the executing pipeline.
	Export the result of the pipeline.

Pipeline Builder

Pipeline Builder allows you to build a simple aggregation pipeline by defining stage operators. It consists of the following sections: Pipeline, Stage Editor, Input/Output Preview, Script Preview.



① Pipeline

A diagram to illustrate the aggregation pipeline. You can see all stages at a glance and add, delete, and move them as needed.

② Stage Editor

The Stage Editor is where you edit the selected stage.

③ Input/Output Preview Pane

The Input Preview and Output Preview panes allow you to view the input documents and results at each stage.

④ Script Preview

You can view the aggregation pipeline script.

Choose Source Collection


The source input of the pipeline is a single collection or view. Select **Source** in the pipeline and fill in the following options.

Option	Description
Source Collection	Choose a collection or view as the source.
Preview Sample Options	Set the limit on the number of sampled documents.


Work with Aggregation Pipeline Stage

You can break down a complex query into easier stages. In each stage, you complete a different operation on the data, such as filtering, grouping, sorting, and transforming. You can check whether your query is functioning properly at every stage by examining both its input and output. There is no limit to the number of stages used in the query, or how you combine them.

Add Stage

1. Hover over an arrow.
2. Click the  icon.

Move Stage

1. Hover over a stage.
2. Click and hold the  icon.
3. Move it to the desired location.

Enable / Disable Stage

1. Hover over a stage.
2. Turn on or off the stage.

Check Stage Input / Output

1. Hover over a stage.
2. Click **Preview**.


Delete Stage

1. Control-click a stage and select **Delete**.

Modify Pipeline Settings

You can click **Option** to view and change pipeline settings.

Pipeline Results

You can click  to execute the pipeline. The **Result** tab should populate with the same results as those found in the last stage output.

Pipeline Explain

You can click  to view the [execution plan](#) that helps you understand the performance of the pipeline.


Chapter 13 - Data Migration Tools

About Data Migration Tools

Navicat provides a number of powerful tools for working with data, including Import Wizard, Export Wizard, Data Transfer, Data Synchronization, Structure Synchronization, Dump SQL File and Execute SQL File. With those tools, you can migrate your data between different servers, databases and formats easily.

Import Wizard

About Import Wizard

Import Wizard allows you to import data to tables/collections from CSV, TXT, XML, DBF and more. You can save your settings as a profile for future use or setting [automation tasks](#). To open the Import Wizard window, click  from the object toolbar.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB.

Note: Lite edition only supports to import text-based files, such as TXT, CSV, XML and JSON.

Hint: You can drag a supported file to the Table/Collection's Objects tab or a database/schema in the Navigation pane. Navicat will pop up the Import Wizard window automatically. If an existing table/collection is highlighted, Navicat will import the file to the highlighted table/collection. Otherwise, it will import the file to a new table/collection.

Choose File Format

Select one of the available import types for the source file.

Choose Files

Click **Add File** or **Add URL** to add import source files. Select the **Encoding** for the source file.

Note: You can add more than one file to import.

ODBC


Setting up an ODBC Data Source Connection

1. Install suitable ODBC Administrator and the corresponding driver for file.
2. In Applications, select **Utilities** -> **ODBC Administrator**; or in Navicat, click the **ODBC Administrator** button in this step.
3. Click the **Add** button in the **User DSN** tab.
4. Select the appropriate ODBC driver and click the **OK** button.
5. Enter required information.

- Click the **Finish** button to see your ODBC Driver in the list.

Note: You can consult with the driver provider about how to setup the DSN.

Connecting to ODBC Data Source in Navicat

- Click  in **Import from**.
- Choose the data source from the **Connection** drop-down menu and provide valid username and password.
- All available tables will be included in the list in the next step if connection is success.

Choose Record Format / File Options

TXT, CSV

Record Delimiter

Specify the record separator of the file.

Delimited

Import the text file with delimited format.

Fixed Width

Import the text file with fixed-width format. To delimit the source column bounds, click on the desired position to create a break line. Simply drag it to move it or double-click it to remove it.

Fixed Width - Fields are aligned in columns with spaces between each field

Lines with arrows signify field breaks. To CREATE a break line, LEFT click at the desired position. To DELETE a break line, RIGHT click on the line. To MOVE a break line, drag it.

JOB_ID	JOB_TITLE	MIN_S
AC_ACCOUNT	Public Accountant	4 2 0 0
AC_MGR	Accounting Manager	8 2 0 0
AD_ASST	Administration Assistant	3 0 0 0
AD_PRES	President	2 0 0 0 0
AD_VP	Administration Vice President	1 5 0 0 0
FI_ACCOUNT	Accountant	4 2 0 0
FI_MGR	Finance Manager	8 2 0 0
HR_REP	Human Resources Representative	4 0 0 0
IT_PROG	Programmer	4 0 0 0
MK_MAN	Marketing Manager	9 0 0 0
MK_REP	Marketing Representative	4 0 0 0
PR_REP	Public Relations Representative	4 5 0 0

Field Delimiter

Specify the field separator.

Text Qualifier

Specify the character that encloses text values.

XML, JSON

Tag that identifies a table row / Tag that identifies a collection row

Define a tag to identify rows.

Consider tag attributes as table field / Consider tag attributes as collection field

For example:

```
<row age="17">
```

```
<id>1</id>
```

```
<name>size</name>
```

```
</row>
```

With this option is on, Navicat will recognize "age" as a field together with "id" and "name", otherwise, only "id" and "name" will be imported as fields.

Note: Navicat does not support multiple level of XML file.

Excel

Sheets will be shown in the list.

ODBC, Access

The **Add Query** button allows you to construct a query to import only certain rows from your source tables. In other words, import only rows that satisfy the criteria set by you. Tables or queries will be shown in the list.

Choose Format Options

The following options depend on the file format chose in the first step.

Field Name Row

Indicate which row should Navicat recognize as field names.

Data Row

Indicate which row should Navicat start and stop reading the actual data.

Note: If no field names are defined for the file, uncheck the Field Name Row option.

Date Format

Specify the format for date.

Four Digit Years

Check this option to display four digits for years.

Date Delimiter

Specify the date separator.

Time Delimiter

Specify the time separator.

Decimal Symbol

Specify the decimal separator for decimal number.

Thousand Separator





Specify the thousand separator for number.

Map Tables / Collections

You are allowed to define a new name or choose to import into an existing table/collection from the drop-down menu.

Note: If you type a new name in **Target Table / Target Collection**, the box in **New Table** will be shown YES automatically.

For importing multiple tables/collections, all tables/collections will be shown in the list.

Source File	Target Table	New Table
countries	 countries	↕
job_history	 job_history	↕
jobs	 jobs	↕
locations	 location	↕ YES

Map Fields

Navicat will make assumption on the field types and length in the source table/collection. You are allowed to choose desired type from the drop-down menu.

Hint: For importing multiple tables/collections, select other tables/collections from the drop-down menu.

category1 <- category (category.xlsx)

Source Field	Target Field	Type	Length	Scale	Primary Key
<input checked="" type="checkbox"/> category_id	category_id	varchar	↕ 255	0	<input type="checkbox"/>
<input checked="" type="checkbox"/> name	name	varchar	↕ 255	0	<input type="checkbox"/>
<input checked="" type="checkbox"/> last_update	last_update	varchar	↕ 255	0	<input type="checkbox"/>

▼
varchar
date
time
timestamp
datetime
tinyblob

If you are importing data into existing tables/collections, you might need to map the source field names manually to the target or control-click and select **Smart Match All**, **Ordinally Match All** and **Unmatch All** from the pop-up menu for quick mapping.

Source Field		Primary Key
customer_id	customer_id	<input checked="" type="checkbox"/>
store_id	store_id	<input type="checkbox"/>
first_name	first_name	<input type="checkbox"/>
last_name	last_name	<input type="checkbox"/>
email	email	<input type="checkbox"/>
address_id	address_id	<input type="checkbox"/>
active	active	<input type="checkbox"/>
create_date	create_date	<input type="checkbox"/>
last_update	last_update	<input type="checkbox"/>

Source Field	Target Field		Primary Key
customer_id	customer_id	↕	<input checked="" type="checkbox"/>
store_id	store_id	↕	<input type="checkbox"/>
first_name	first_name	↕	<input type="checkbox"/>
last_name	last_name	↕	<input type="checkbox"/>
email	email		
address_id	address_id		
active	active		
create_date	create_date		
last_update	last_update		

If you are importing via ODBC, the **Condition Query** button opens the **WHERE** dialog where you can specify a *WHERE* clause to import only certain rows from your source. In other words, import only rows that satisfy the criteria set by you.

Hint: Do not include the word *WHERE* in the clause.

Choose Import Mode

Select the import mode that defines how the data being imported.

Import Mode:

- Append:** add records to the destination table
- Update:** update records in the destination with matching records from source
- Append/Update:** if records exist in destination, update it. Otherwise, add it
- Delete:** delete records in destination that match records in source
- Copy:** delete all records in destination, repopulate from the source

Hint: To activate the remaining options, you must enable Primary Key in the previous step.

Source Field	Target Field		Primary Key
country_id	country_id	↕	<input checked="" type="checkbox"/>
country	country	↕	<input type="checkbox"/>
last_update	last_update	↕	<input type="checkbox"/>

Click the **Advanced** button for more settings. The following options depend on the connection server type.

Run multiple queries in each execution

Execute multiple SQL statements at once, which will make the import process faster.

Use extended insert statements

Insert records using extended insert syntax.

Example:

```
INSERT INTO `users` VALUES ('1', 'Peter McKindsy', '23'), ('2', 'Johnson Ryne', '56'), ('0', 'Katherine', '23');
```

Maximum statement size

Specify the maximum size (in KB) of individual extended INSERT statement that can be executed. If the row size exceeds this value, a normal INSERT statement will be used.

Use empty string as NULL

Import NULL value if the source data field contains empty string.

Ignore foreign key constraint

Ignore the checking of foreign key constraints during the import process.

Continue on error

Ignore errors that are encountered during the import process.

Save and Start Import


Click the **Start** button to begin the import process. The wizard will display the import progress, execution time, and success or failure messages.

After the import process finished, you can click the **View Log** button to open the log file.

Hint: Click the **Save Profile** button to save your settings as a profile.

Export Wizard

About Export Wizard

Export Wizard allows you to export data from tables, collections, views, or query results to any available formats. You can save your settings as a profile for future use or setting [automation tasks](#). To open the Export Wizard window, click  from the object toolbar.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB.

Note: Lite edition only supports to export text-based files, such as TXT, CSV, HTML, XML, SQL and JSON.

Choose File Format

Select one of the available export formats for the target file.

Choose Saving Path

You can set the exported file name and location in this step. Click the **Change** button to change the default export location.

Check the box next to the object name that you want to export. The highlighted object in the object pane is checked automatically. The file extension changes according to the selected export type in the first step. If you are exporting selected objects into the same target file, set them with the same file name, you can control-click the grid and select **Export Selected to Same File**. When the file format is Excel, each object will be exported as a sheet in the Excel file.

Note: For exporting query results, ensure the query is saved before running Export Wizard. Otherwise, no source object displayed in here.

Encoding

Select the encoding for the exported file.

Add timestamp

Check this option if you want your file name specifies the timestamp of the export is run. Select the date/time format from the drop-down menu.

Choose Table / Collection Fields

You can select what fields to export. All the fields are selected in the list by default. If you want to omit some fields to be exported, uncheck the **All fields** option first and then uncheck those fields in the list.

Note: For exporting query result, the wizard will skip this step.

Choose Additional Options

The following options depend on the file format chose in the first step.

Include column titles

Field names will be included into the exported file if this option is on.

Blank if zero

Leave it blank if the field content is 0.

Append on output file(s)

Append records to the existing file

Continue on error

Ignore errors that are encountered during the export process.

Use Attributes Format in XML

Attributes Format
<pre><RECORDS> <RECORD OrderNo="1003" ItemNo="1" PartNo="1313" Qty="5" Discount="0"></RECORD> <RECORD OrderNo="1004" ItemNo="1" PartNo="1313" Qty="10" Discount="50"></RECORD> </RECORDS></pre>
Non-Attributes Format
<pre><RECORDS> <RECORD> <OrderNo>1003</OrderNo> <ItemNo>1</ItemNo> <PartNo>1313</PartNo> <Qty>5</Qty> <Discount>0</Discount> </RECORD> <RECORD> <OrderNo>1004</OrderNo> <ItemNo>1</ItemNo> <PartNo>1313</PartNo> <Qty>10</Qty> <Discount>50</Discount> </RECORD> </RECORDS></pre>

Export as legacy format (with "RECORDS" key)

Legacy Format
<pre>{ "RECORDS": [{ "COUNTRY_ID": AR "COUNTRY_NAME": "Argentina" "REGION_ID": 2 }, { "COUNTRY_ID": AU "COUNTRY_NAME": "Australia" "REGION_ID": 3 }] }</pre>
New Format

```
[
  {
    "COUNTRY_ID": AR
    "COUNTRY_NAME": "Argentina"
    "REGION_ID": 2
  },
  {
    "COUNTRY_ID": AU
    "COUNTRY_NAME": "Australia"
    "REGION_ID": 3
  }
]
```

Record Delimiter, Field Delimiter, Text Qualifier

Specify the record separator, the field separator and the character that encloses text values.

Zero padding date

Add a leading zero to pad days and months to two digits if necessary.

Date Order, Date Delimiter

Specify the format for date and the date separator.

Time Delimiter

Specify the time separator.

Decimal Symbol

Specify the decimal separator for decimal number.

Binary Data Encoding

Set binary data are exported as Base64 encoded or no encoding in the file.

Save and Start Export

Click the **Start** button to begin the export process. The wizard will display the export progress, execution time, and success or failure messages.

Hint: Click the **Save Profile** button to save your settings as a profile.

Data Transfer (Available only in Navicat Premium, Enterprise and Standard Edition)

About Data Transfer

Navicat allows you to transfer objects from one database/schema to another, or to a sql file (RDBMS) or a Javascript file (MongoDB). The target database and/or schema can be on the same server as the source or on another server. To open the Data Transfer window, choose **Tools -> Data Transfer** from the menu bar.

You can save your settings as a profile for future use or setting [automation tasks](#). To open a saved profile, click the **Load Profile** button and select a profile from the list.


Hint: Profiles are saved under the default path, e.g. ~/Library/Application Support/PremiumSoft CyberTech/Navicat CC/Common/Profiles

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB.

Hint: You can drag tables/collections to a database/schema in the Navigation pane. If the target database/schema is within the same connection, Navicat will copy the tables/collections directly. Otherwise, Navicat will pop up the Data Transfer window.

Choose Connections & Advanced Options (Step 1)

Choose Source and Target Connections

In the Data Transfer window, define connections, databases and/or schemas for **Source Database** and **Target Database**. You can click  to swap the source and target settings.

You can also transfer your selected database objects directly to a text file. Select the **File** option. Choose the target path, **SQL Format** and **Encoding** for the file.

Note: Navicat Premium supports transferring table with data across different server types, e.g. from MySQL to Oracle. If the source connection is MongoDB, Navicat Premium only can transfer data to MongoDB server.

Choose Advanced Options

Then, click the **Options** button to set the advanced options. The options depend on the source and target connection server types and sort in ascending order.

Continue on error

Ignore errors that are encountered during the transfer process.

Convert object name to

Check this option if you require convert object names to **Lower case** or **Upper case** during the process.

Create collections

Check this option if you want to create collections in the target database. Suppose this option is unchecked and collections already exist in the target database, then all data will be appended to the destination collections.

Create tables

Check this option if you want to create tables in the target database. Suppose this option is unchecked and tables already exist in the target database/schema, then all data will be appended to the destination tables.

Create target database/schema if not exist

Create a new database/schema if the database/schema specified in the target server does not exist.

Drop target objects before create

Check this option if database objects already exist in the target database and/or schema, the existing objects will be deleted once the data transfer starts.

Drop with CASCADE

Check this option if you want to drop the dependent database objects with the cascade option.

Include auto increment

Include auto increment in the table with this option is on.

Include character set

Include character set in the table with this option is on.

Include checks

Include checks in the table with this option is on.

Include definers

Include the definers of the objects with this option is on.

Include engine/table type

Include table type with this option is on.

Include excludes

Include exclusion constraints in the table with this option is on.

Include foreign key constraints

Include foreign keys in the table with this option is on.

Include indexes

Include indexes in the table with this option is on.

Include other collection options

Include other options in the collection with this option is on.

Include other table options

Include other options in the table with this option is on.

Include owners

Include the owners of the objects with this option is on.

Include rules

Include rules in the table with this option is on.

Include triggers

Include triggers in the table with this option is on.

Include uniques

Include uniques in the table with this option is on.

Insert records

Check this option if you require all records to be transferred to the destination database and/or schema.

Lock source tables

Lock the tables in the source database and/or schema during the data transfer process.

Lock target tables

Lock the tables in the target database and/or schema during the data transfer process.

Maximum statement size

Specify the maximum size (in KB) of individual extended INSERT statement that can be executed. If the row size exceeds this value, a normal INSERT statement will be used.

Use complete insert statements

Insert records using complete insert syntax.

Example:

```
INSERT INTO `users` (`ID Number`, `User Name`, `User Age`) VALUES ('1', 'Peter McKindsy', '23');
```

```
INSERT INTO `users` (`ID Number`, `User Name`, `User Age`) VALUES ('2', 'Johnson Ryne', '56');
```

```
INSERT INTO `users` (`ID Number`, `User Name`, `User Age`) VALUES ('0', 'katherine', '23');
```

Use DDL from SHOW CREATE TABLE

If this option is on, DDL will be used from SHOW CREATE TABLE.

Use DDL from sqlite_master

If this option is on, DDL will be used from the SQLITE_MASTER table.

Use delayed insert statements

Insert records using DELAYED insert SQL statements.

Example:

```
INSERT DELAYED INTO `users` VALUES ('1', 'Peter McKindsy', '23');
```

```
INSERT DELAYED INTO `users` VALUES ('2', 'Johnson Ryne', '56');
```

```
INSERT DELAYED INTO `users` VALUES ('0', 'katherine', '23');
```

Use extended insert statements

Insert records using extended insert syntax.

Example: `INSERT INTO `users` VALUES ('1', 'Peter McKindsy', '23'), ('2', 'Johnson Ryne', '56'), ('0', 'Katherine', '23');`

Use hexadecimal format for BLOB

Insert BLOB data as hexadecimal format.

Use ignore insert statements

Insert records using IGNORE insert SQL statements. All ignorable errors that occur while executing INSERT statements will be ignored.

Use replace insert statements

Insert records using REPLACE SQL statements. If a row in the target table has the same value as the source for a PRIMARY KEY or a UNIQUE index, the row in the target is deleted before the new row is inserted.

Use single transaction

Check this option if you want to use a single transaction during the data transfer process.


Use transaction

Check this option if you want to use transaction during the data transfer process.

Choose Objects & Transfer Mode (Step 2)

Choose Objects to Transfer

All the database objects are unselected in the **Database Objects** list by default. Check the database objects that you want to transfer.



(*)	All the database objects being transferred to the target database/schema, all newly added database objects will also be transferred without amending the data transfer profile.
(#/#)	Only the checked database objects will be transferred. However, if you add any new database objects in the source database and/or schema after you create your data transfer profile, the newly added database objects will not be transferred unless you manually modify the Database Objects list.

Choose Transfer Mode for Tables / Views

You can customize the **Transfer Mode** for the selected table/view. If you choose **Auto**, Navicat will transfer the table/view using the default settings. If you want to customize the transfer settings, choose **Advanced** and set the following options:

Option	Description
Target Name	Enter the name of the table / view that will be created in the target database.
All fields	Transfer all fields in the table.
Custom fields	You can choose which fields to transfer. Click + and select the fields. Change the name of the target field if necessary.

All rows	Transfer all records in the table.
Number of rows per batch	Specify the number of rows of data per batch. If it is not enabled, all data in the table is sent to the target server as a single transaction.
Custom recordsets	Filter the records for transfer. Click + and enter an expression.
Recordset Generator	If your table is large, you may want to divide it to several record sets to avoid connection timeout. The Recordset Generator can divide the records into a number of recordsets as evenly as possible between the start and end values of a field. Set Field Name , Start Value , End Value and Number of Recordsets in the pop-up window.
SQL Preview	Show the SQL statements for returning the recordsets.
Use transaction for each recordset	Use a transaction for each recordset during the data transfer process.
Transfer as table	The view will be transferred to the target database as a new table.

Confirm & Start Data Transfer (Step 3)

A summary table lists all selected objects that is being transferred to the target database.

Continue on error

Ignore errors that are encountered during the transfer process.

Drop target objects before create

Check this option if database objects already exist in the target database and/or schema, the existing objects will be deleted once the data transfer starts.

Start Data Transfer

Click the **Start** button to execute the data transfer process. The window will display the execution progress, execution time, and success or failure messages.

Data Synchronization (Available only in Navicat Premium, Enterprise and Standard Edition)

About Data Synchronization

Navicat allows you to transfer data from one database and/or schema to another with detailed analytical process. In other words, Navicat provides the ability for data in different databases and/or schemas to be kept up-to-date so that each repository contains the same information. To open the Data Synchronization window, choose **Tools** -> **Data Synchronization** from the menu bar.

You can save your settings as a profile for future use or setting [automation tasks](#). To open a saved profile, click the **Load Profile** button and select a profile from the list.


Hint: Profiles are saved under the default path, e.g. ~/Library/Application Support/PremiumSoft CyberTech/Navicat CC/Common/Profiles

Note: SQL Server 2000 does not support this feature. For Oracle server, BLOB, CLOB, NCLOB, LONG and LONG RAW data are skipped during the data synchronization process. TIMESTAMP primary key cannot synchronize (insert, update) with Database Link to 9i server. RAW primary key cannot synchronize (insert, update, delete) with Database Link to any server, without error.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB. Navicat Premium and Navicat for MySQL support synchronizing between MySQL and MariaDB.

Choose Connections & Comparing Options (Step 1)

Choose Source and Target Connections

In the Data Synchronization window, define connections, databases and/or schemas for **Source Database** and **Target Database**. You can click  to swap the source and target settings.

Choose Comparing Options

Then, click the **Options** button to set the comparing options.

Insert

Insert records if the records do not exist in the target.

Delete

Delete extra records from the target.

Update

Update the target if the record is different from the source.

Choose Table / Collection Mapping (Step 2)

In this step, only tables/collections which contain identical names between the source and target are mapped in the list by default. If you do not want some tables/collections to be synchronized, disable them manually from the drop-down menu.

Keys and fields which contain identical names are also mapped. You can change the mapping in the **Key Mapping** and **Field Mapping** columns.

After mapping the tables/collections, click **Compare & Preview** to view the comparison results (Step 3). If you want to skip the preview and deploy immediately, click **Compare & Deploy**.

View Data Comparison Results (Step 3)

After comparing data, the window shows the number of records that will be inserted, updated or deleted in the target. Uncheck the **Show identical table and others** / **Show identical collection and others** option to hide the tables/collections with identical data and the tables/collections with different structures. All tables/collections with different data and all actions are checked by default. Uncheck the checkbox that you do not want to apply to the target.

MySQL sakila		MySQL sakila3					
<input checked="" type="checkbox"/> Show identical table and others							
Source Table	Target Table	Insert	Update	Delete	Same	Message	
<input checked="" type="checkbox"/> actor	actor	<input checked="" type="checkbox"/> 0	<input checked="" type="checkbox"/> 1	<input checked="" type="checkbox"/> 0	<input checked="" type="checkbox"/> 199		
<input checked="" type="checkbox"/> category	category	<input checked="" type="checkbox"/> 0	<input checked="" type="checkbox"/> 0	<input checked="" type="checkbox"/> 0	<input checked="" type="checkbox"/> 0	Different number...	
<input checked="" type="checkbox"/> film_category	film_category	<input checked="" type="checkbox"/> 1	<input checked="" type="checkbox"/> 0	<input type="checkbox"/> 0/1	<input checked="" type="checkbox"/> 999		
<input checked="" type="checkbox"/> language	language	<input checked="" type="checkbox"/> 0	<input checked="" type="checkbox"/> 0	<input checked="" type="checkbox"/> 1	<input checked="" type="checkbox"/> 6		
<input checked="" type="checkbox"/> payment	payment	<input checked="" type="checkbox"/> 0	<input checked="" type="checkbox"/> 1	<input checked="" type="checkbox"/> 0	<input checked="" type="checkbox"/> 1604		
<input type="checkbox"/> rental	rental	<input checked="" type="checkbox"/> 0	<input type="checkbox"/> 0/2	<input checked="" type="checkbox"/> 0	<input checked="" type="checkbox"/> 1604		
<input checked="" type="checkbox"/> sales	sales	<input checked="" type="checkbox"/> 0	<input checked="" type="checkbox"/> 0	<input checked="" type="checkbox"/> 0	<input checked="" type="checkbox"/> 0	Source table do n...	

When you selected a table/collection in the list, the bottom pane shows data in the source and target. Values that differ between the source and target are highlighted. To view multiple lines data, control-click the grid and select **Show Assistant Viewer**. Uncheck the records that you do not want to apply to the target.

Choose an option from the drop-down menu to show the data.

Option	Description
All Rows	Show all records in the source and target.
Difference	Show all records that are different in the source and target.
Insert	Only show the records that do not exist in the target.
Update	Only show the records that exist in both source and target, but they have different values.
Delete	Only show the records that do not exist in the source.
Same	Show the records that exist in both source and target and they have identical values.

Difference

payment				payment					
	rental_id	amount	payment_date	last_update		rental_id	amount	payment_date	last_update
<input checked="" type="checkbox"/>	1185	5.99	2005-06-15 00:00:00	2006-02-15	<input type="checkbox"/>	1185	6.99	2005-06-15 00:00:00	2021-09-27
<input checked="" type="checkbox"/>	2363	0.99	2005-06-18 13:30:00	2006-02-15	<input type="checkbox"/>	2363	1.99	2005-06-18 13:30:00	2021-09-27
<input checked="" type="checkbox"/>	11299	3.99	2005-08-02 15:30:00	2006-02-15	<input type="checkbox"/>	11299	2.99	2005-08-02 15:30:00	2021-09-27
<input checked="" type="checkbox"/>	11367	0.99	2005-08-02 18:00:00	2006-02-15	<input type="checkbox"/>	11367	4.99	2005-08-02 18:00:00	2021-09-27

Click the **Next** button to show the scripts of all selected tables/collections and records.

Edit & Execute Selected Scripts (Step 4)

You can view all scripts that will be executed in the target database in the **Deployment Script** tab.

Deployment Options Button	Description
Deployment Options	<p>Use transaction - Rollback all data when error occurs.</p> <p>Continue on error - Ignore errors that are encountered during the execution process if necessary.</p>

	<p>Run multiple queries in each execution - Execute multiple SQL statements at once, which will make the synchronization process faster.</p> <p>Include deployment query in message log - Show all executed queries in the Message Log tab.</p>
Edit Script	Open the Edit Deployment Script window to rearrange the order of the scripts.
Copy Script to Clipboard	Copy all scripts from the Deployment Script tab to the clipboard.
Open Script in Query Editor	Open a new query window and display the scripts.

In the **Edit Deployment Script** window, use the arrow buttons to move the scripts.

Then, click the **Start** button to execute the scripts. The window will display the execution progress, execution time, and success or failure messages.

Structure Synchronization (Available only in Navicat Premium, Enterprise and Standard Edition)

About Structure Synchronization

Navicat allows you to compare and modify the table structures and other objects with detailed analytical process. In other words, Navicat compares objects between two databases and/or schemas and states the differential in structure. To open the Structure Synchronization window, choose **Tools** -> **Structure Synchronization** from the menu bar.


You can save your settings as a profile for future use. To open a saved profile, click the **Load Profile** button and select a profile from the list.

Hint: Profiles are saved under the default path, e.g. ~/Library/Application Support/PremiumSoft CyberTech/Navicat CC/Common/Profiles

Note: Available only for MySQL, Oracle, PostgreSQL, SQL Server and MariaDB. Navicat Premium and Navicat for MySQL support synchronizing between MySQL and MariaDB.

Choose Connections & Comparing Options (Step 1)

Choose Source and Target Connections

In the Structure Synchronization window, define connections, databases and/or schemas for **Source Database** and **Target Database**. You can click  to swap the source and target settings.

Choose Comparing Options

Then, click the **Options** button to set the database/schema comparing options. The options depend on the connection server type and sort in ascending order.

Compare auto increment value

Check this option if you want to compare the auto increment values of tables.

Compare character set

Check this option if you want to compare the character sets of tables.

Compare checks

Check this option if you want to compare checks.

Compare collation

Check this option if you want to compare the collations of tables.

Compare definers

Check this option if you want to compare the definers.

Compare events

Check this option if you want to compare events.

Compare excludes

Check this option if you want to compare table excludes.

Compare foreign keys

Check this option if you want to compare table foreign keys.

Compare functions

Check this option if you want to compare functions.

Compare identity last value

Check this option if you want to compare the identity last values of tables.

Compare indexes

Check this option if you want to compare indexes.

Compare owners

Check this option if you want to compare the owners of the objects.

Compare partitions

Check this option if you want to compare table partitions.

Compare primary keys

Check this option if you want to compare table primary keys.

Compare rules

Check this option if you want to compare rules.

Compare sequences

Check this option if you want to compare sequences.

Compare storage

Check this option if you want to compare storage.

Compare table options

Check this option if you want to compare other table options.

Compare tables

Check this option if you want to compare tables.

Compare tablespace and physical attributes

Check this option if you want to compare tablespace and physical attributes.

Compare triggers

Check this option if you want to compare triggers.

Compare uniques

Check this option if you want to compare table uniques.

Compare views

Check this option if you want to compare views.

Drop with CASCADE

Check this option if you want to drop the dependent database objects with the CASCADE option.

Identifier Case Sensitivity

Ignore or consider the case of identifiers when mapping, or use the server default setting.

Start Comparison

Click the **Compare** button to compare the source and target databases.

View Structure Comparison Results (Step 2)

After comparing structures, the tree view shows the differences between the source and target databases or schemas. Check the objects you want to apply to the target. You can expand the table objects to view the detailed structure.

Source Object	Operation	Target Object
Objects to be modified (3 of 3 selected)		
category		category
category_id	+	
name	+	
last_update	+	
		Quater
		Type
		Amount
(Primary Key)	+	
(Table Options)	→	(Table Options)

DDL Comparison	Deployment Script
<pre> 1 CREATE TABLE `sakila`.`category` (2 `category_id` tinyint UNSIGNED NOT NULL AUTO_INCREMENT, 3 `name` varchar(25) CHARACTER SET utf8 COLLATE utf8_general_ci, 4 `last_update` timestamp NOT NULL DEFAULT CURRENT_TIMESTAMP ON 5 PRIMARY KEY (`category_id`) USING BTREE 6) ENGINE = InnoDB AUTO_INCREMENT = 17 CHARACTER SET = utf8 COLL </pre>	<pre> 1 CREATE TABLE `sakila3`.`category` (2 `Quater` varchar(255) CHARACTER SET utf8mb4 COLLATE utf8mb4_ 3 `Type` varchar(255) CHARACTER SET utf8mb4 COLLATE utf8mb4_ 4 `Amount` int NULL DEFAULT NULL 5) ENGINE = InnoDB CHARACTER SET = utf8mb4 COLLATE = utf8mb4_ </pre>

You can choose to group the objects in the tree views by object types or operations by selecting **Group by Object Type** or **Group by Operation**.

Operation	Description
→	Object exists in both source and target databases/schemas, but they have different definition. The target object will be modified based on the source object.
+	Object does not exist in the target database/schema. It will be created in the target.
×	Object does not exist in the source database/schema. The target object will be deleted.
=	Object exists in both source and target databases/schemas and they have identical definition. No operation will be applied.

When you selected an object in the tree view, the **DDL Comparison** tab shows the DDL statements of that object in the source and the target, and the **Deployment Script** tab shows the detailed SQL statements of the object that will be executed in the target databases.

Click the **Next** button to show the scripts of all selected objects.

Edit & Execute Selected Scripts (Step 3)

You can view all scripts that will be executed in the target database in the **Deployment Script** tab.

Deployment Options Button	Description
Deployment Options	<p>Continue on error - Ignore errors that are encountered during the execution process if necessary.</p> <p>Include deployment query in message log - Show all executed queries in the Message Log tab.</p>
Edit Script	Open the Edit Deployment Script window to rearrange the order of the scripts.

Copy Script to Clipboard	Copy all scripts from the Deployment Script tab to the clipboard.
Open Script in Query Editor	Open a new query window and display the scripts.

In the **Edit Deployment Script** window, use the arrow buttons to move the scripts.

Then, click the **Start** button to execute the scripts. The window will display the execution progress, execution time, and success or failure messages.

Dump & Execute SQL / Script File

The **Dump SQL File**, **Execute SQL File**, **Dump Script File** and **Execute Script File** features allow you to dump your database, schema, tables or collections to a SQL or .js file or execute SQL or .js files in your connection, database or schema.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB.

To dump a file

1. In the main window, control-click an opened database/schema or control-click the selected tables/collections, and select **Dump SQL File** or **Dump Script File** -> **Structure Only** or **Structure + Data**.
2. Browse the save location and enter a file name.
3. Click **Save**.

Hint: After the dump process finished, you can click the **Open** button to open the file using Query Editor.

To execute a file

1. In the main window, control-click an opened connection, database or schema and select **Execute SQL File** or **Execute Script File**.
2. Browse your SQL or .js file, choose the encoding of the file and enable appropriate options.

Option	Description
Continue on error	Ignore errors that are encountered during the execution process.
Run multiple queries in each execution	Execute multiple SQL statements at once, which will make the execution process faster.
SET AUTOCOMMIT=0 / No Auto Commit	Disable auto commit mode.

3. Click **Start**.

Hint: You can drag and drop a .sql or .js file to an opened connection, database or schema in the Navigation pane. Navicat will pop up the Execute SQL File or Execute Script File window automatically.

Execute Command File

The **Execute Command File** feature allow you to execute Redis command file (.redis) in your connection or database.

Note: Available only for Redis.

To execute a file

1. In the main window, control-click an opened connection or database and select **Execute Command File**.
2. Browse your .redis file, choose the encoding of the file and enable appropriate options.

Option	Description
Batch Size	Specify the maximal number of commands in a batch.
Continue on error	Ignore errors that are encountered during the execution process.

3. Click **Start**.

Hint: You can drag and drop a .redis file to an opened connection or database in the Navigation pane. Navicat will pop up the Execute Command File window automatically.

MongoImport & MongoExport

About MongoImport & MongoExport

MongoDB provides two utilities for import and export data: MongoImport and MongoExport. You can import or export the data according to the specified conditions.

MongoImport

MongoImport allows you to import data from a JSON, CSV or TSV file into MongoDB database.

Note: You must have [mongoimport](#) executable for this feature to work.

To import a file

1. In Navicat main window, control-click your database and select **MongoImport**.
2. In the **General** and **Advanced** tabs, select the input file path, the target collection, the file type, and the appropriate import options.
3. Click the **Start** button to begin the import process. The **Message Log** tab will display the import progress, execution time, and success or failure messages.

You can save your settings as a profile for future use or setting [automation tasks](#). To open a saved profile, click the **Load Profile** button and select a profile from the list.

Hint: Profiles are saved under the default path, e.g. ~/Library/Application Support/PremiumSoft CyberTech/Navicat CC/Common/Profiles

MongoExport

MongoExport allows you to export MongoDB collections to a JSON or CSV file.

Note: You must have [mongoexport](#) executable for this feature to work.

To export collections

1. In Navicat main window, control-click your database and select **MongoExport**.
2. In the **General** and **Advanced** tabs, select the export file path, the source collection, the file type, and the appropriate export options.
3. Click the **Start** button to begin the export process. The **Message Log** tab will display the export progress, execution time, and success or failure messages.

You can save your settings as a profile for future use or setting [automation tasks](#). To open a saved profile, click the **Load Profile** button and select a profile from the list.

Hint: Profiles are saved under the default path, e.g. ~/Library/Application Support/PremiumSoft CyberTech/Navicat CC/Common/Profiles

Chapter 14 - Data Generation (Available only in Navicat Premium, Enterprise and Standard Edition)

About Data Generation

With the column-intelligent data generation, you can populate selected tables with realistic and meaningful test data. The generated data in one column is based on the data in another. You can populate empty tables, or add extra rows to your existing tables, and control over the creation of the foreign key data. To open the Data Generation window, choose **Tools -> Data Generation** from the menu bar.

You can save your settings as a profile for future use or setting [automation tasks](#). To open a saved profile, click the **Load Profile** button and select a profile from the list.

Hint: Profiles are saved under the default path, e.g. ~/Library/Application Support/PremiumSoft CyberTech/Navicat CC/Common/Profiles

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB.

Choose Target Connection (Step 1)

Choose Target Connection

In the Data Generation window, define the target connection, database and/or schema.

Choose Advanced Options

Then, click the **Options** button to set the advanced options. The options depend on the target connection server type and sort in ascending order.

Continue on error

Ignore errors that are encountered during the data generation process.

Empty collections before generating data

Remove all data in the target collections before generating data.

Empty tables before generating data

Remove all data in the target tables before generating data.

Run multiple insert statements

Execute multiple INSERT statements at once, which will make the execution process faster.

Use extended insert statements

Insert records using extended insert syntax.

Example: `INSERT INTO `users` VALUES ('1', 'Peter McKindsy', '23'), ('2', 'Johnson Ryne', '56'), ('0', 'Katherine', '23');`


Use transaction

Check this option if you want to use transaction during the data generation process.

Choose Objects & Column Properties (Step 2)

Choose Objects to Populate

All tables are unselected in the Database Objects list by default. Check the tables and columns that you want to populate.



You can copy all the settings from one object and paste the settings to other objects by control-clicking an object in the list.

Choose Table / Collection Properties

You can specify the volume of the data you want to generate for each table/collection.

Navicat did not take dependencies into account when defining the order in which tables/collections data will be generated. Click the **Table Generation Order/Collection Generation Order** button to change the order if necessary.

Choose Column Properties

Navicat automatically assigns a generator to each column based on its table name, column name, data type, and length. Use the **Generator** combo box to select a generator from the list.

The following table shows the common properties.

Option	Description
Include default values	Generate default values. You can set the default value of the column, and set the Percentage of the default values in the column.

Include null values	Generate NULL values. You can set the Percentage of Null values in the column.
Set unique	Make the values generated for the column unique.
Convert value to	Convert the values to lower case, upper case or proper case (the first letter in each word is capitalized, the other letters are lower case).
Disable data linkage between fields	Unlink the data between this field with other fields. If this option is unchecked, Navicat will generate data with linkage between fields. Example: If the name field is "Robert Rose", the email field will be like "robertrose@outlook.com".

Use Generator (Step 2.1)

Number Generator

The Number Generator generates numeric values such as integers and decimal numbers.

Generator:

Start:

End:

Number Type: Integer
 Decimal Number

Decimal Places:

Preview: 792
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Start	Specify the minimum numeric value.
End	Specify the maximum numeric value.
Number Type	Choose the type of the numeric values: Integer or Decimal Number.

Date / Time / DateTime Generator

The Date / Time / DateTime Generator generates dates and/or times.

Generator: Date Time

Start Date: ...

End Date: ...

Whole Day

Start Time: ...

End Time: ...

Day of the Week: All

Weekday

Custom

Mon Tue Wed Thu

Fri Sat Sun

Preview: 2019-07-19 21:22:46

[Refresh](#)

Generator Properties

You can customize the generator by changing its properties. The properties depend on the generator you are chosen.

Option	Description
Start Date	Specify the minimum date value.
End Date	Specify the maximum date value.
Whole Day	Include any time of the day.
Start Time	Specify the minimum time value.
End Time	Specify the maximum time value.
Day of the Week	Choose the day of the week for the date value.

Sequence Generator

The Sequence Generator generates randomized sequences of integers.

Generator: Sequence

Start:

Increment:

Min

Max

Cycle

Preview: 1

[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Start	Specify first number in the sequence.
Increment	Specify the value added to the current sequence value to create a new value.
Min	Specify the lower bound of the sequence range.
Max	Specify the upper bound of the sequence range.
Cycle	The sequence continues to generate values after reaching either its maximum or minimum value.

Enum Generator

The Enum Generator generates values from specified value list.

Generator:

Values:

Preview:
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Values	Specify the values. Values are generated from the existing data of the column, where applicable.

Text Generator

The Text Generator generates dummy text values.

Generator:

Number of Characters: -

Preview:


Generator Properties

You can customize the generator by changing its properties:

Option	Description
Number of Characters	Specify the minimum and maximum number of characters.

Image/Binary Generator

The Image/Binary Generator generates images and Binary data, or randomly imports files in a specified folder.

Generator: 

Data From: Image Generator


Image Width:

Image Height:

Image Format: JPEG

PNG

Randomly Pick From Folder

Folder Path: 

Filter with Extensions:

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Image Generator	
Image Width	Specify the width of the image.
Image Height	Specify the height of the image.
Image Format	Choose the image file format.
Randomly Pick From Folder	
Folder Path	Specify a folder containing a number of images or binary data files.
Filter with Extensions	Specify the extension list for the files that are being imported.

Foreign Key Generator

The Foreign Key Generator generates foreign key values for a child table field based on the values contained in a parent table field.

Generator: Foreign Key

Schema: sakila

Table: address

Field: address_id

Generation Mode:
 Random
 No Repeat
 Repeat each values from 1 to 3 times

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Schema	Choose the schema of the parent table.
Table	Choose a parent table.
Field	Choose a field in the parent table. Make sure that the child table column and the parent table column have compatible types.
Generation Mode	Choose the generation mode of the data: random data, no repeated data or specified number of repetitions.

UUID Generator

The UUID Generator generates a set of universally unique identifiers (UUIDs) based on the specified format.

Generator: UUID

UUID Format:
 Include hyphens
 No format

Regular Expression:

```

((0-9a-f){8})-([0-9a-f]{4})-([0-9a-f]{4})-
([0-9a-f]{4})-([0-9a-f]{12})

```

Preview: 968caa97-c867-39b6-fbdf-c22e6a18f872
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
UUID Format	Generate UUIDs with or without hyphens.
Regular Expression	Edit the regular expression. For more information about regular expression, see Regular Expression Generator .

Regular Expression Generator

The Regular Expression Generator generates values based on a regular expression.

Generator: Regular Expression

Regular Expression:

Preview: `9cOywA9dCu`
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Regular Expression	Enter the regular expression.

Syntax Elements


The following table shows the syntax elements.


Description	Example	Generates
Basic		
ordinary chars	Kelly	Kelly
individual chars	[AB]	A or B
initial] in char set	[[]]]
[x-y] range	[0-9]	e.g. 2 or 7
[chars] character set	[A-Z0-9]	e.g. 3 or M
[exclude chars] character set	[^abc]	e.g. m or [
* zero or more	abc*	e.g. abcc or ab
+ 1 or more	abc+	e.g. abcccc or abc
? Include or not	abc?	ab or abc
(regexp) grouping	(abc)*d	e.g. abcabcd or d
{num} repeat	b{4}	bbbb
{min,max} repeat	b{3,4}	bbb or bbbb
{min,} at least min repeats	b{4,}	e.g. bbbb or bbbbbbbbb
() empty string	()	
alternatives	True False	True or False
empty alternative	th(e is at)	e.g. the or that
Escapes		

backslash	\\	\
dot	\.	.
caret	\^	^
dollar sign	\\$	\$
left curly bracket	\{	{
right curly bracket	\}	}
left square bracket	\[[
right square bracket	\]]
left parenthesis	\((
right parenthesis	\))
vertical bar	\	
asterisk	*	*
plus mark	\+	+
question mark	\?	?
upper or lower-case letter or underscore or digit	\w	[A-Za-z_0-9]
all ASCII printable characters	\W	[~]
digit	\d	[0-9]
carriage return	\r	
tab character	\t	
space character	\s	

Name Generator

The Name Generator generates first, last or full names in English, Chinese or Japanese.

Generator: 

Format Type: 

Languages: English

- Chinese (Pinyin)
- Chinese (简体中文)
- Chinese (Eng)
- Chinese (繁體中文)
- Japanese (Romaji)
- Japanese (日本語)

Preview: **Wong Sai Wing**
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Format Type	Generate first names, last names or full names.
Languages	Select the language of the names.

Gender Generator

The Gender Generator generates different genders in English, Chinese or Japanese.

Generator:

Languages: English
 Chinese (简体中文)
 Chinese (繁體中文)
 Japanese (日本語)

Preview: M
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the genders.

Title Generator

The Title Generator generates different titles in English, Chinese or Japanese.

Generator:

Languages: English
 Chinese (简体中文)
 Chinese (繁體中文)
 Japanese (日本語)

Preview: Mrs.
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the titles.

Marital Status Generator

The Marital Status Generator generates different marital status types in English, Chinese or Japanese.

Generator:

Languages: English
 Chinese (简体中文)
 Chinese (繁體中文)
 Japanese (日本語)

Preview: **Married**
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the marital status.

Phone Number Generator

The Phone Number Generator generates random phone numbers which follow the phone number rules.

Generator:

Format:

Include delimiters

Regions: United States
 United Kingdom
 China
 Japan
 Others

Preview: **(20) 9786 7396**
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Format	Choose the format of the phone numbers. If you choose to generate international phone numbers, the country code will be added.
Include delimiters	Add delimiters to the phone numbers.

Regions	Select the region of the phone numbers.
---------	---

Email Generator

The Email Generator generates emails with the specified domain names.

Generator:

Domains:

Preview: ikmori426@gmail.com
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Domains	Enter a list of email domain names.

Job Title Generator

The Job Title Generator generates different job titles in English, Chinese or Japanese.

Generator:

Languages: English
 Chinese (简体中文)
 Chinese (繁體中文)
 Japanese (日本語)

Preview: Business reporter
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the job titles.

Social Network ID Generator

The Social Network ID Generator generates random social network account names.

Generator: Social network ID

Preview: saiwingwo
[Refresh](#)

Payment Method Generator

The Payment Method Generator generates payment methods from specified value list.

Generator: Payment Method

Values: Credit Card
PayPal
Apple Pay

Preview: PayPal
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Values	Specify the payment methods.

Credit Card Type Generator

The Credit Card Type Generator generates types of credit cards.

Generator: Credit Card Type

Types: American Express
 JCB
 MasterCard
 UnionPay
 Visa

Preview: MasterCard
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Types	Select the credit card types.

Credit Card Number Generator

The Credit Card Number Generator generates credit card numbers for different credit card types.

Generator:

Types: American Express
 JCB
 MasterCard
 UnionPay
 Visa

Preview: 5097867396226180
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Types	Select the credit card type.

Credit Card Date Generator

The Credit Card Date Generator generates the issuance dates or expiration dates of credit cards.

Generator:

Date Type:

Date Range: / - /

Preview: 07/04
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Date Type	Generate issuance dates or expiration dates.

Date Range	Choose the date range (MM/YY - MM/YY).
------------	--

Company Name Generator

The Company Name Generator generates company names in English, Chinese or Japanese.

Generator:

Languages: English
 Chinese (Pinyin)
 Chinese (简体中文)
 Chinese (Eng)
 Chinese (繁體中文)
 Japanese (Romaji)
 Japanese (日本語)

Preview: **Wong Kee Telecommunication Limited**
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the company names.

Department Generator

The Department Generator generates company department names in English, Chinese or Japanese.

Generator:

Languages: English
 Chinese (简体中文)
 Chinese (繁體中文)
 Japanese (日本語)

Preview: **Sales**
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the department names.

Industry Generator

The Industry Generator generates industry names in English, Chinese or Japanese.

Generator:

Languages: English
 Chinese (简体中文)
 Chinese (繁體中文)
 Japanese (日本語)

Preview: Engineering industry
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the industry names.

Address Generator

The Address Generator generates line 1, line 2 or full addresses of US, UK, China or Japan.

Generator:

Type:

Regions: United States
 United Kingdom
 China (English)
 Japan (English)
 China (简体中文)
 Japan (日本語)

Preview: 281 Regent Street
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Type	Generate line 1, line 2 or full addresses.
Regions	Select the region of the addresses.

City Generator

The City Generator generates city names in US, UK, China or Japan.

Generator:

Regions: United States
 United Kingdom
 China
 Japan
 Others

Languages: English
 Chinese (简体中文)
 Chinese (繁體中文)
 Japanese (日本語)

Preview: **Shanghai**
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Regions	Select the region of the cities.
Languages	Select the language of the city names.

Region Generator

The Region Generator generates region names or ISO 3166 country codes in English, Chinese or Japanese.

Generator:

Format:

Languages: English
 Chinese (简体中文)
 Chinese (繁體中文)
 Japanese (日本語)

Preview: **Australia**
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Format	Generate region names, ISO 3166-1 alpha-2 or ISO 3166-1 alpha-3 country codes.
Languages	Select the language of the region names.

Product Name Generator

The Product Name Generator generates product names with the specified keywords.

Generator:

Generate with keywords:

Preview: Rambutan
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Generate with keywords	Specify keywords for generating the product names.

Product Category Generator

The Product Category Generator generates product category names in English, Chinese or Japanese.

Generator:

Languages: English
 Chinese (简体中文)
 Chinese (繁體中文)
 Japanese (日本語)

Preview: Computers & Electronics
[Refresh](#)


Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the category names.

Color Generator

The Color Generator generates color names in English, Chinese or Japanese.

Generator: 

Languages: English
 Chinese (简体中文)
 Chinese (繁體中文)
 Japanese (日本語)

Preview: **Khaki**
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the color names.

Size Generator

The Size Generator generates size (XS / S / M / L / XL) in English, Chinese or Japanese.

Generator: 

Languages: English
 Chinese (简体中文)
 Chinese (繁體中文)
 Japanese (日本語)

Preview: **S**
[Refresh](#)


Generator Properties

You can customize the generator by changing its properties:

Option	Description
Languages	Select the language of the size.

Weight Unit Generator

The Weight Unit Generator generates weight units from specified value list.

Generator: 

Values:

Preview: **kg**
[Refresh](#)


Generator Properties

You can customize the generator by changing its properties:

Option	Description
Values	Specify the weight units.

Barcode Generator

The Barcode Generator generates barcodes based on different barcode types or the specified format.

Generator: 

Types: EAN8
 EAN13
 UPCA
 UPCE
 ISBN
 Code39

Regular Expression:

Preview: **6897867396223**
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Types	Select the barcode types. You can customize Code39 barcode format in the Regular Expression box. For more information about regular expression, see Regular Expression Generator .

SKU Generator

The SKU Generator generates stock keeping units (SKU) based on the specified format.

Generator:

Regular Expression:

Preview: BA-EC-9786-H
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Regular Expression	Edit the regular expression. For more information about regular expression, see Regular Expression Generator .

IP Address Generator

The IP Address Generator generates IPv4 or IPv6 addresses.

Generator:

IP Address Type: IPv4
 IPv6

Regular Expression:

Preview: 78.252.197.250
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
IP Address Type	Generate IPv4 or IPv6 addresses.
Regular Expression	Edit the regular expression. For more information about regular expression, see Regular Expression Generator .

MAC Address Generator

The MAC Address Generator generates random MAC addresses with the specified format.

Generator: MAC Address

Regular Expression: `(([0-9a-f]{2};){5})([0-9a-f]{2})`

Preview: `96:8c:aa:97:c8:67`
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Regular Expression	Edit the regular expression. For more information about regular expression, see Regular Expression Generator .

File Path Generator

The File Path Generator generates file paths for Windows, macOS or Linux.

Generator: File Path

Path type: Windows
 MacOS
 Linux
 Include file name

Extension Type: Image

Extensions: `jpg`
`png`

Preview: `C:\Users\Administrator\Pictures\img_863398.png`
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Path type	Select the OS type of the file paths.
Include file name	Append file names to the end of the paths.
Extension Type	Choose the file extension type.
Extensions	Edit the file extensions.

File Name Generator

The File Name Generator generates file names.

Generator:

Include extension

Extension Type:

Extensions:

Preview: [img_863398.png](#)
[Refresh](#)


Generator Properties


You can customize the generator by changing its properties:

Option	Description
Include extension	Append file extensions to the file names.
Extension Type	Choose the file extension type.
Extensions	Edit the file extensions.

File Extension Generator

The File Extension Generator generates file extensions.

Generator: File Extension 

Extension Type: Image 

Extensions:

jpg
png

Preview: png
[Refresh](#)


Generator Properties

You can customize the generator by changing its properties:

Option	Description
Extension Type	Choose the file extension type.
Extensions	Edit the file extensions.

URL Generator

The URL Generator generates URLs with the specified subdomains and top-level domains.

Generator: URL 

Subdomain:

auth.
drive.
image.
video.
www.

Top-Level-Domain:

.biz
.co.jp
.com
.cn
.info
.jp
.net
.org
.us

Preview: <https://video.ziyi923.cn/Appliances>
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Subdomain	Enter a list of website subdomains.
Top-Level-Domain	Enter a list of top-level domains.

Hostname Generator

The Hostname Generator generates server hostnames with the specified subdomains and top-level domains.

Generator:

Subdomain:

Top-Level-Domain:

Preview: [video.lkmori426.co.jp](#)
[Refresh](#)

Generator Properties

You can customize the generator by changing its properties:

Option	Description
Subdomain	Enter a list of website subdomains.
Top-Level-Domain	Enter a list of top-level domains.

Preview Data & Start Generation (Step 3)

You can preview the data that will be generated for each table.

Click the **Start** button to execute the data generation process. The window will display the execution progress, execution time, and success or failure messages.

Chapter 15 - Data Dictionary (Available only in Navicat Premium, Enterprise and Standard Edition)

About Data Dictionary

Data Dictionary helps you manage and document your database systems efficiently. It acts as a centralized repository of metadata, providing comprehensive information about the structure, relationships, and properties of the database objects. You can create a data dictionary at server, database, schema level. To open the Data Dictionary window, choose **Tools -> Data Dictionary** from the menu bar.

You can save your settings as a profile for future use or setting [automation tasks](#). To open a saved profile, click the **Load Profile** button and select a profile from the list.

Hint: Profiles are saved under the default path, e.g. ~/Library/Application Support/PremiumSoft CyberTech/Navicat CC/Common/Profiles

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB.

Choose Databases (Step 1)

In the Data Dictionary window, select the databases and/or schemas you want to generate data dictionary.

Choose Objects & Change Order (Step 2)

In the list, choose objects to include in the data dictionary.

Navicat will generate the data dictionary contents based on the sequence of the objects on the list. You can select the objects and use the arrow buttons to change the order.

Choose Template (Step 3)

Navicat provides several templates for data dictionary files. You can choose the appropriate template and follow the remaining steps to customize your settings.

Adjust Layout Settings (Step 4)

You can adjust the layout of the template and view the preview on the left pane.

Layout Properties

Option	Description
Cover	

Include cover	Add a cover page.
Header Logo	Insert a preceding image in the header.
Header	Enter a header that appears once at the top of the cover page.
Title	Enter the title of the data dictionary.
Subtitle	Enter the subtitle of the data dictionary.
Remarks	Enter remarks that appear on the cover page.
Background Image	Default - Use the default background image. Custom - Insert a background image for the cover page. None - Explicitly not insert a background image.
Footer	Enter a footer that appears once at the bottom of the cover page.
Table of Contents	
Include table of contents	Add table of contents to the data dictionary.
Header/Footer	
Include breadcrumbs header	Add a breadcrumbs header that appears at the top of every page except the cover and table of contents.
Heading Font	Set the font style of the heading.
Subheading Font	Set the font style of the subheading.
Include left footer	Add a footer that appears at the bottom left of every page except the cover, table of contents and introduction.
Include page number in right footer	Add page numbers to the right footer of every page except the cover, table of contents and introduction.
Footer Font	Set the font style of the footer.
Main Content	
Include Introduction	Add a page for introducing the data dictionary.
Introduction	Enter the introduction.
Font	Set the font style of the introduction.
Paper	
Paper	Choose the paper size.
Orientation	Select a page orientation (Portrait or Landscape).
Margin (CM)	Set the margins of the document.

Set File Path & Start Generation (Step 5)

Set File Path & Other Options

Option	Description
Export To File	Specify the path of the data dictionary file.
Append timestamp to file name	Append timestamp information to the file name to show when the file is created.
Overwrite existing file	Overwrite if the file already exists.
Continue on error	Ignore errors that are encountered during the generation process.


Start Generation

Click the **Start** button to generate the data dictionary. The window will display the generation progress, time, and success or failure messages.

After the generation process finished, you can click the **Open** button to open the data dictionary file

Chapter 16 - BI (Available only in Navicat Premium and Enterprise Edition)

About BI

BI feature is designed to help you extract insights and make data-driven decisions by providing powerful data visualization, reporting, and analytics capabilities. In the main window, click  **BI** to open the workspace object list.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB, MongoDB and Snowflake. Snowflake is only available in Navicat Premium.

Some of key features are listed here:

- Support more than 20 chart types.
- Customize multiple pages dashboard.
- Visualize live data.
- Add interactive controls.

Hint: Workspace files (.nbi) are saved under the default path, e.g. ~/Library/Application Support/PremiumSoft CyberTech/Navicat CC/Navicat Premium/Profiles. To open the folder, control-click a workspace file and select **Show in Finder**. If the workspace is synchronized to [Navicat Cloud](#) or [On-Prem Server](#), it will be stored in the cloud.

Open an external workspace file

1. In the menu bar, choose **File -> Open External File -> BI Workspace**.
2. Browse the file and click **Open** in the dialog window.

Save an opened external file as a Navicat workspace


1. In Workspace Designer, choose **File -> Save to Navicat**.
2. Enter the workspace name and choose the save location.
3. Click **OK**.

Save a Navicat workspace as an external file

1. In Workspace Designer, choose **File -> Save As External File**.
2. Choose the save path and enter the file name.
3. Click **Save**.

Workspace

A workspace is the place that comprises dashboards, charts and data sources. You can create multiple dashboards, charts and data sources in a workspace.





1 Workspace Toolbar

The Workspace Toolbar provides controls that you can use to create data sources, charts and dashboards.

2 Tab Bar

The Tab Bar allows you to switch among the opened items.

3 Content Pane


The Content pane shows all items in the workspace. Use the  **Detail** or  **Icon** button to change the view.


Detail View displays additional information about each item. You can sort items in Detail View, click the column header by which you want to sort the items.

Icon View displays your items as a grid of thumbnail images. You can filter the items by clicking a category (All, Data Source, Chart, Dashboard) in this view.

4 Properties Pane

The  **General** tab shows the general information of the workspace or the selected item.

The  **Using** tab shows the items that the selected item depends on.


The  **Used By** tab shows the items that depend on the selected item.

If the Properties pane is hidden, choose **View -> Show Properties** from the menu bar.

Data Source

About Data Source

Data sources reference tables in your connections or data in files/ODBC sources, and can select data from tables on different server types. The fields in the dataset can be used to construct a chart. When building a chart, you will need to specify the data source that the chart uses.



1 Connections Pane

The Connections pane is the basic way to navigate with connections, databases, tables, queries.

2 Data Source Toolbar

The Data Source Toolbar provides controls that you can use to manipulate the data.

3 Design Pane


The Design pane allows you to build the data source visually.

Navicat provides two modes for connecting your data: Live and Archive.


Live mode retrieves data from your servers whenever the data source is being used / loaded. It offers the convenience of real-time updates, with any changes in the underlying data reflected.

Archive mode retrieves data from your servers during the data source creation, and stored the retrieved data in the workspace for later use by building charts.

4 Preview Pane

The Preview pane displays the data of the data source. You can click the  icon to show or hide the columns.

5 Properties Pane


The  **Properties** tab shows the general information of the data source. You can add a remark to the data source.

The  **Used By** tab shows the charts that depend on the data source.


If the Properties pane is hidden, choose **View -> Show Properties** from the menu bar.


Create Data Source

The essential steps to create a data source are:

1. In the Workspace window, click .
2. Enter the name of the data source and select the desired connections, files or existing data sources.

Option	Description
Database	Create data source using existing connections in Navicat, or create a new connection in the workspace. For more information about connection settings, see Connections .
File/ODBC	Import data to the workspace, or link the data source to the data in a supported external file or ODBC source. For more information about import steps, see Import Wizard .
Recent Connections	Choose the connections used in other existing data sources in the workspace.

3. Click **OK**.
4. A tab will open for you to edit the data source.
5. If you want to add more connections, click **+** and follow the steps.
6. Drag and drop tables from the Connections pane to the Design pane. You can view the table data by clicking .
7. Drag and drop a node to another to create the join.
8. Configure the join type and join fields if necessary.




Hint: After creating the join, you can change the join settings at any time by clicking the join icon on the connector.

9. Choose **Live** mode or **Archive** mode.
10. Click **Apply and Refresh Data** to view the data.



Add Query to Database Connection

For database connections, you can save query results to create a new dataset.

To create a new query

1. On the Connections pane, double-click  **New Data Source Query**.
2. Write the statement in [Query Editor](#). You can also use [Query Builder](#) to build the query visually.
3. Click **Save Query**.
4. Enter the name of the query and click **Save**.


To add an existing query

1. On the Connections pane, double-click  **New Data Source Query**.
2. Click .
3. Select a query.
4. Click **Import**.
5. Click **Save Query**.
6. Enter the name of the query and click **Save**.



Add Aggregation Pipeline to Database Connection

For MongoDB database connections, you can save aggregation pipeline results to create a new dataset.

To create a new pipeline

1. On the Connections pane, double-click  **New Data Source Aggregation Pipeline**.
2. Build the pipeline using [Pipeline Builder](#).
3. Click **Save Pipeline**.
4. Enter the name of the pipeline and click **Save**.

To add an existing pipeline

1. On the Connections pane, double-click  **New Data Source Aggregation Pipeline**.
2. Click .
3. Select a pipeline.
4. Click **Import**.
5. Click **Save Pipeline**.
6. Enter the name of the pipeline and click **Save**.

Modify Data Source Connections

My Connections

To change a connection in My Connections to a workspace connection

1. On the Connections pane, control-click a connection and select **Convert to Workspace Connection**.
2. The connection will be moved to the "Workspace" section.

To recreate a not found connection

If the server connection in My Connections was removed, it will be moved to the "Not Found in My Connections" section. You may need to recreate the connection in order to connect the server.

1. On the Connections pane, control-click a connection and select **Recreate Connection in My Connections**.
2. Enter the connection properties.
3. Click **OK**.

Project Connections

To change a project connection to a workspace connection

1. On the Connections pane, control-click a connection and select **Convert to Workspace Connection**.
2. The connection will be moved to the "Workspace" section.

To recreate a not found connection

If the server connection in the project was removed, it will be moved to the "Not Found in Project" section. You may need to recreate the connection in order to connect the server.

1. On the Connections pane, control-click a connection and select **Recreate Connection in Project**.
2. Enter the connection properties.
3. Click **OK**.

Workspace Connections

To edit the settings of a database connection

1. On the Connections pane, control-click a database connection and select **Edit Connection**.
2. Follow the steps to edit the connection.

To change the user password of a database connection

1. On the Connections pane, control-click a database connection and select **Change Connection Password**.
2. Enter the database user password.
3. Click **OK**.

To edit the settings of a file connection

1. On the Connections pane, control-click a file connection and select **Edit File Connection Settings**.
2. Follow the steps to edit the connection.


To change the path of a linked file connection

1. On the Connections pane, control-click a file connection and select **Change Linked File Path**.
2. Follow the steps to edit the connection.

Filter / Sort / Project Data

If your data source has many data or fields, you may find it easier to limit the data or fields to just the ones you want so you can simplify the data selections.

Filter Data

Filter pane allows you to facilitate creating and applying filter criteria that you specify for the data. Click  from the toolbar to activate the Filter pane.

1. To add a new condition to the criteria, just simply click . If you want to add a condition with parentheses, click .

Hint: To add parentheses to existing conditions, simply control-click on the selected conditions and select **Group with Bracket**. To remove the parentheses, control-click a bracket and select **Delete Bracket** or **Delete Bracket and Conditions**.

2. Click on the field name (next to the checkbox) and choose a field from the list.
3. Click on the operator (next to the field name) and choose a filter operator.


Filter Operator	Operator Description
=	The field is equal to 'value'.
!=	The field is not equal to 'value'.
<	The field is less than 'value'.
<=	The field is less than or equal to 'value'.
>	The field is greater than 'value'.
>=	The field is greater than or equal to 'value'.
contains	The field contains 'value'.
does not contain	The field does not contain 'value'.
begin with	The field starts with 'value'.
does not begin with	The field does not start with 'value'.
end with	The field ends with 'value'.
does not end with	The field does not end with 'value'.
is null	The field is NULL.
is not null	The field is NOT NULL.
is empty	The field is empty.
is not empty	The field is not empty.
is between	The field is between 'value1' and 'value2'.
is not between	The field is not between 'value1' and 'value2'.
is in list	The field is in the list of ('value1','value2',...).
is not in list	The field is not in the list of ('value1','value2',...).

4. Click on **<?>** to activate the appropriate editor and enter the criteria values. The editor used in the criteria values box is determined by the data type assigned to the corresponding field.
5. Click on the logical operator (next to the criteria values) to choose **and** or **or**.
6. Repeat step 1-5 to add another new condition.
7. Click **Apply & Refresh Data** to see the result of the filtering you made.


Hint: If you want to reverse the meaning of the conditions, control-click the selected conditions and select **Toggle Negator**.


Sort Data

Navicat offers the ability to sort and order data. Click  from the toolbar to activate the Sort pane.

1. To add a new criteria, just simply click ..
2. Click on the field name (next to the checkbox) and choose a field from the list.
3. Click on the sorting order to choose **ASC** or **DESC**.
4. Repeat step 1-3 to add another new criteria.
5. Click **Apply & Refresh Data** to see the result of the sorting you made.

Project Data

You can choose which fields to include or exclude in the data source. Click  from the toolbar to activate the Projection pane.

1. Choose to **Include** or **Exclude** fields.
2. To add a new criteria, just simply click ..
3. Click on the field name (next to the checkbox) and choose a field from the list.
4. Repeat step 2-3 to add another new criteria.
5. Click **Apply & Refresh Data** to see the result of the projection you made.


Add Custom Fields

You can extend your data with customized fields. New fields can be created by changing the field type, concatenating other fields, mapping to other values or sorting based on another field/customized order.

Create Custom Field

Type-Changed Field


Field types (String, Number, Date/Time) are assigned to every field based on the actual data type of the field. If the field was not interpreted correctly, you can adjust the field type.

1. In the bottom data grid, select a field and click  -> **Type-Changed Field** to get started.
2. In the pop-up window, enter the **Target Field Name**.
3. Choose the **Target Field Type**.

4. Choose the **Source Field Name**.
5. Set the **Source Field Data Format** if necessary.
6. Click **OK**.


Concatenated Field

You can add a new field and concatenate the data from two already existing fields.

1. In the bottom data grid, select a field and click  -> **Concatenated Field** to get started.
2. In the pop-up window, enter the **Name** of the target field.
3. Double-click a field on the **Source Fields** pane to add it to the body.
4. Edit the body and enable the **Set null if all field values are null or empty** option if necessary.
5. Click **OK**.


Mapped Field

You can create a new field populated with the results of applying a mapping rule on every value in the source field.

1. In the bottom data grid, select a field and click  -> **Mapped Field** to get started.
2. In the pop-up window, enter the **Target Field Name**.
3. Choose the **Source Field Name**.
4. Click **Add** to create a new mapping rule.
5. Enable the **Compare source values with case sensitive** option if necessary.
6. Choose the action for the values that are not in the mapping rules.
7. Click **OK**.

Custom-Sorted Field


You can create a new field to rearrange the order of the values, based on another field, or a custom order. When you sort this new field in the chart, it will be sorted in the order you set.

1. In the bottom data grid, select a field and click  -> **Custom-Sorted Field** to get started.
2. In the pop-up window, enter the **Target Field Name**.
3. Choose the **Source Field Name**.
4. [Reference Field] Choose the field which the sort order of the target field will be based on.

5. [Custom Sort] Customize the order of the field values by moving the values to the **Sorted Values** list.
6. Click **OK**.

Calculated Field

You can create a new field with a custom expression. You can use functions, fields and operators in the expression.

1. In the bottom data grid, select a field and click  -> **Calculated Field** to get started.
2. In the pop-up window, enter the **Target Field Name**.
3. Enter an expression in the **Body** text box.
4. Click **OK**.

Edit Custom Field

1. In the bottom data grid, control-click on the customized field and select **Edit field_name**.
2. In the pop-up window, modify the field properties.
3. Click **OK**.

Delete Custom Field


1. In the bottom data grid, control-click on the customized field and select **Remove field_name**.

Chart

About Chart

A chart provides visual representations of the data in your data source. It maps to a single data source, and can display correlations between several fields in the data. You can even make the chart interactive by adding a control chart.

Note: You must add a [data source](#) before you can begin building charts.



1 Data Source Pane

The Data Source pane is the basic way to navigate with the data sources. If the Data Source pane is hidden, choose **View -> Show Data Source** from the menu bar.

2 Chart Toolbar

The Chart Toolbar provides controls that you can use to manipulate the data.

3 Metric Pane

The Metric pane allows you to choose the chart type and add fields to the shelves from the Data Source Pane. If the Metric pane is hidden, choose **View -> Show Metric** from the menu bar.

4 Preview Pane

The Preview pane displays the chart.

5 Properties Pane

The **Properties** tab includes the basic layout settings, data format settings and so on. The properties vary with the type of the chart.


The **Using** tab shows the data sources that the chart depends on.

The **Used By** tab shows the dashboards that depend on the chart.

If the Properties pane is hidden, choose **View -> Show Properties** from the menu bar.

Build Chart

The essential steps to create a chart are:

1. In the Workspace window, click .
2. Select the data source and enter the name of the chart.
3. A tab will open for you to edit the chart.
4. Choose the [Chart Type](#) on the middle pane.




Hint: The type of chart you will use is normally determined by the type of the data.

5. Drag fields to the corresponding shelf in the Metric pane to set axis, values, etc.
6. Select the properties on the right pane which can be further customized for your chart.

Hint: Each chart type has different properties.


7. The chart shows on the Preview pane.



Set Field Alias

You can create aliases for fields so that their labels appear differently in the chart.

1. Click the down arrow in the field box.
2. Select **Set Alias**.



3. Enter the alias name.

Filter / Sort Data


Filter Source Data in Chart

You can use the [Data Filter](#) pane to filter the source data in the current chart.


Filter Display Data in Chart

You can filter the display data in 3 ways:

- Click the down arrow in the field box and select **Display Filter**.



- Use the [Display Filter](#) pane.
- Control-click a series / data points on the chart.




Hint: If you want to clear the filter, you need to use the Display Filter pane.

Sort Data

You can sort the data in 2 ways:

- Click the down arrow in the field box and select **Sort**.




- Use the [Sort](#) pane.

Apply Aggregate Function

Aggregate functions allow you to summarize or change the granularity of your data.

1. Click the down arrow in the field box.



2. Select **Aggregate** and choose a aggregate function.


Function	Description
Number	
Sum	Return the sum of all values. Null values are ignored.
Average	Return the average of all the values. Null values are ignored.
Count	Return the number of items. Null values are not counted.
Count(Distinct)	Return the number of distinct items. Null values are not counted.
Min	Return the minimum value across all records. Null values are ignored.
Max	Return the maximum value across all records. Null values are ignored.
Median	Return the median value across all records. Null values are ignored.
DateTime	
Count	Return the number of items. Null values are not counted.
Count(Distinct)	Return the number of distinct items. Null values are not counted.
Year	Return the year of the date (0000-9999).
Quarter	Return the year of the date (0000-9999) and the quarter of the year (Q1-Q4).
Month	Return the year (0000-9999) and the month (01-12) of the date.
Week	Return the year of the date (0000-9999) and the week of the year (W01-W52, start of week is Sunday).
Day	Return the date.

Hour	Return the date and the hour of the time (00-23).
Minute	Return the date, the hour of the time (00-23) and the minute of the time (00-59).
Second	Return the datetime.
Quarter (Extract)	Return the quarter of the year (Q1-Q4).
Month (Extract)	Return the month of the date (01-12).
Week (Extract)	Return the week of the year (W01-W52, start of week is Sunday).
Day (Extract)	Return the day of the date (01-31).
Hour (Extract)	Return the hour of the time (00-23).
Minute (Extract)	Return the minute of the time (00-59).
Second (Extract)	Return the second of the time (00-59).
Text	
First	Return the value of the first record.
Last	Return the value of the last record.
Count	Return the number of items. Null values are not counted.
Count(Distinct)	Return the number of distinct items. Null values are not counted.

Add Range

You can aggregate data into ranges without the need to create any additional calculations in the data source.

1. Click the down arrow in the field box.



2. Select **Add Range**.
3. Edit the range settings.


Option	Description
Range Type - Fixed	
Bin Size	Either enter the size of a bin or click Calculate to let Navicat calculate a value for you.
Range Type - Custom	
Stop Values	Add the bin boundaries.

4. Click **OK**.

Set Value Operation

You can create a chart that shows a running total as values are added or subtracted.


1. Click the down arrow in the field box.



2. Select **Value Operation** and choose an operation.

Operation	Description
Cumulative	Sum the values cumulatively.
Subtract	Subtract the value with its previous value.

Present Chart

You can present the chart using the whole screen. The title bar, toolbars, tab bar, Data Source pane, Metric pane and Properties pane will be hidden while in this mode. To open a chart in present view, click  **Present**.

To exit present view, press the ESC key and the workspace window will be returned to its previous state.

Sort Chart


In the Present mode, you can organize your data in a chart with one click. You can sort data series by a value. Simply click the  icon to sort on a different value and select the sorting order.

Chart Types

About Chart Types

Navicat provides a variety of different chart types so data can be displayed in a meaningful way.

Here is a complete list of available chart types:

- Vertical Bar Chart
- Vertical Stacked Bar Chart
- Horizontal Bar Chart
- Horizontal Stacked Bar Chart
- Line Chart
- Area Chart
- Stacked Area Chart

- Bar and Line Chart
- Stacked Bar and Line Chart
- Waterfall Chart
- Tornado Chart
- Pie Chart
- Donut Chart
- Scatter Chart
- Heatmap
- Treemap
- Value
- Trend
- KPI
- Gauge
- Table
- Pivot Table
- Control

Bar Chart

A bar chart provides high-level overviews of data trends by comparing values within a specific category.

- Vertical Bar Chart
- Vertical Stacked Bar Chart
- Horizontal Bar Chart
- Horizontal Stacked Bar Chart







Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Align	Set the vertical or horizontal alignment of the legend.
Label Color	Set the color of the legend labels.
Data	
Show Bar Labels	Display the data labels of the selected series.
Bar Label Contains	Display the data values or/and the percentages on the labels.
Bar Label Position	Set the position of the bar labels.
Use 100% stacked	Use 100% stacked bars to show values for hierarchical data. (Each bar height is 100%, and the colored bar segments represent the components' relative contributions to the total bar.)
Bar Label Font	Set the font style of the bar labels.
Use custom data value color	Customize the color of the labels of the data values.

Positive Data Value Color	Set the color of the positive value labels.
Negative Data Value Color	Set the color of the negative value labels.
Show only top #	Only the top # data are displayed.
Style	Plot discrete or continuous data series on the chart.
Density	Choose the density of the data series.
Color	Set the color palette of the data series.
All Data Colors	Allow setting the color for each series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
X-Axis	
Show X-Axis title	Display the title of X-Axis.
X-Axis Title	Specify the title of X-Axis.
Font	Set the font style of X-Axis title.
Show X-Axis title at the end of axis	Display the title at the end of X-Axis.
Show X-Axis labels	Display labels on X-Axis.
Font / Bold	Set the font style of X-Axis labels.
X-Axis Label Rotation	Rotate X-Axis labels.
X-Axis Label Interval	Change the interval between X-Axis labels.
Show X-Axis	Display X-Axis line.
X-Axis Color	Set the color of X-Axis line.
Y-Axis	
Show Y-Axis title	Display the title of Y-Axis.
Y-Axis Title	Specify the title of Y-Axis.
Font	Set the font style of Y-Axis title.
Show Y-Axis title at the end of axis	Display the title at the end of Y-Axis.
Show Y-Axis labels	Display labels on Y-Axis.
Font / Bold	Set the font style of Y-Axis labels.
Show Y-Axis	Display Y-Axis line.

Y-Axis Color	Set the color of Y-Axis line.
Show grid line	Display the grid line of Y-Axis.
Use custom range	Set the range of the grid lines. Enter values in Start and End . The graph drawing beyond this range will be clipped off.
Use custom interval	Change the Interval on Y-Axis.
Tick Interval	Set the interval of the tick marks in axis units.
Assistant Line	
	Add an assistant line to the chart to show visual data trends, averages, normal distributions, etc.
	Remove the selected assistant line.
	Rename the selected assistant line.
Value	Select a data series for the assistant line.
Group Value	Select a group value for the assistant line.
Type	Choose the type of assistant line you want.
Show R ² value	Display the R ² value on the chart.
Forward Forecast / Backward Forecast	Specify the number of periods to include in a forecast.
Align with other lines	Align the assistant line with others.
Period	Specify the number of data points used to average the point value.
Smooth	Smooth the angles of the line.
Use custom color	Customize the color of the line.
Line Color	Set the color of the line.
Cap Style	Choose the cap style of the line.
Dash Style	Choose the dash style of the line.
Join Style	Choose the join style of the line.
Visible	Check this box to show the line.

Line / Area Chart

A line or area chart displays information as a series of data points connected by straight line segments.

- Line Chart
- Area Chart
- Stacked Area Chart







Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Align	Set the vertical or horizontal alignment of the legend.
Label Color	Set the color of the legend labels.
Data	
Use smoothed line	Plot a smooth line through the data points.
Show Line Labels / Show Area Labels	Display the data labels of the selected series.
Line Label Contains	Display the data values or/and the percentages on the labels.
Line Label Pattern	Select the values that will be displayed on the chart.
Show markers	Display the marker points on the line / area.
Use 100% stacked	Use 100% stacked areas to show values for hierarchical data. (The area height is 100%, and the colored area segments represent the components' relative contributions to the total area.)

Use custom data value color	Customize the color of the labels of the data values.
Positive Data Value Color	Set the color of the positive value labels.
Negative Data Value Color	Set the color of the negative value labels.
Show only top #	Only the top # data are displayed.
Density	Choose the density of the data series.
Color	Set the color palette of the data series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
X-Axis	
Show X-Axis title	Display the title of X-Axis.
X-Axis Title	Specify the title of X-Axis.
Font	Set the font style of X-Axis title.
Show X-Axis title at the end of axis	Display the title at the end of X-Axis.
Show X-Axis labels	Display labels on X-Axis.
Font / Bold	Set the font style of X-Axis labels.
X-Axis Label Rotation	Rotate X-Axis labels.
X-Axis Label Interval	Change the interval between X-Axis labels.
Show X-Axis	Display X-Axis line.
X-Axis Color	Set the color of X-Axis line.
Y-Axis	
Show Y-Axis title	Display the title of Y-Axis.
Y-Axis Title	Specify the title of Y-Axis.
Font	Set the font style of Y-Axis title.
Show Y-Axis title at the end of axis	Display the title at the end of Y-Axis.
Show Y-Axis labels	Display labels on Y-Axis.
Font / Bold	Set the font style of Y-Axis labels.
Show Y-Axis	Display Y-Axis line.

Y-Axis Color	Set the color of Y-Axis line.
Show grid line	Display the grid line of Y-Axis.
Use custom range	Set the range of the grid lines. Enter values in Start and End . The graph drawing beyond this range will be clipped off.
Use custom interval	Change the Interval on Y-Axis.
Tick Interval	Set the interval of the tick marks in axis units.
Assistant Line	
	Add an assistant line to the chart to show visual data trends, averages, normal distributions, etc.
	Remove the selected assistant line.
	Rename the selected assistant line.
Value	Select a data series for the assistant line.
Group Value	Select a group value for the assistant line.
Type	Choose the type of assistant line you want.
Show R ² value	Display the R ² value on the chart.
Forward Forecast / Backward Forecast	Specify the number of periods to include in a forecast.
Align with other lines	Align the assistant line with others.
Period	Specify the number of data points used to average the point value.
Smooth	Smooth the angles of the line.
Use custom color	Customize the color of the line.
Line Color	Set the color of the line.
Cap Style	Choose the cap style of the line.
Dash Style	Choose the dash style of the line.
Join Style	Choose the join style of the line.
Visible	Check this box to show the line.

Bar and Line Chart

Mixing bar and line chart in the same visual is a good way to emphasize the difference between series while still maintaining their relationship.

- Bar and Line Chart
- Stacked Bar and Line Chart







Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Align	Set the vertical or horizontal alignment of the legend.
Label Color	Set the color of the legend labels.
Data	
Use smoothed line	Plot a smooth line through the data points.
Show Labels	Display the data labels of the selected series.
Bar Label Contains	Display the data values or/and the percentages on the labels.
Bar Label Position	Set the position of the bar labels.
Bar Label Font	Set the font style of the bar labels.
Use 100% stacked bar	Use 100% stacked bars to show values for hierarchical data. (Each bar height is 100%, and the colored bar segments represent the components' relative contributions to the total bar.)
Line Label Contains	Display the data values or/and the percentages on the labels.
Line Label Pattern	Select the values that will be displayed on the chart.

Show line markers	Display the marker points on the line.
Use custom data value color	Customize the color of the labels of the data values.
Positive Data Value Color	Set the color of the positive value labels.
Negative Data Value Color	Set the color of the negative value labels.
Show only top #	Only the top # data are displayed.
Style	Plot discrete or continuous data series on the chart.
Density	Choose the density of the data series.
Color	Set the color palette of the data series.
All Bar Data Colors	Allow setting the color for each series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
X-Axis	
Show X-Axis title	Display the title of X-Axis.
X-Axis Title	Specify the title of X-Axis.
Font	Set the font style of X-Axis title.
Show X-Axis title at the end of axis	Display the title at the end of X-Axis.
Show X-Axis labels	Display labels on X-Axis.
Font / Bold	Set the font style of X-Axis labels.
X-Axis Label Rotation	Rotate X-Axis labels.
X-Axis Label Interval	Change the interval between X-Axis labels.
Show X-Axis	Display X-Axis line.
X-Axis Color	Set the color of X-Axis line.
Y-Axis / Secondary Y-Axis	
Show Y-Axis title / Show Secondary Y-Axis title	Display the title of Y-Axis.
Y-Axis Title / Secondary Y-Axis Title	Specify the title of Y-Axis.
Font	Set the font style of Y-Axis title.

Show Y-Axis title at the end of axis / Show Secondary Y-Axis title at the end of axis	Display the title at the end of Y-Axis.
Show Y-Axis labels / Show Secondary Y-Axis labels	Display labels on Y-Axis.
Font / Bold	Set the font style of Y-Axis labels.
Show Y-Axis / Show Secondary Y-Axis	Display Y-Axis line.
Y-Axis Color / Secondary Y-Axis Color	Set the color of Y-Axis line.
Show grid line	Display the grid line of Y-Axis.
Use custom range	Set the range of the grid lines. Enter values in Start and End . The graph drawing beyond this range will be clipped off.
Use custom interval	Change the Interval on Y-Axis.
Tick Interval	Set the interval of the tick marks in axis units.
Assistant Line	
	Add an assistant line to the chart to show visual data trends, averages, normal distributions, etc.
	Remove the selected assistant line.
	Rename the selected assistant line.
Value	Select a data series for the assistant line.
Group Value	Select a group value for the assistant line.
Type	Choose the type of assistant line you want.
Show R ² value	Display the R ² value on the chart.
Forward Forecast / Backward Forecast	Specify the number of periods to include in a forecast.
Align with other lines	Align the assistant line with others.
Period	Specify the number of data points used to average the point value.
Smooth	Smooth the angles of the line.
Use custom color	Customize the color of the line.
Line Color	Set the color of the line.
Cap Style	Choose the cap style of the line.
Dash Style	Choose the dash style of the line.
Join Style	Choose the join style of the line.
Visible	Check this box to show the line.

Waterfall Chart

A waterfall chart is a special type of bar chart. It is useful for understanding how the starting value is affected by a series of changes (increase or decrease).




Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Align	Set the vertical or horizontal alignment of the legend.
Label Color	Set the color of the legend labels.
Data	
Show data values	Display the values of the data series.
Bar Label Position	Set the position of the bar labels.
Bar Label Font	Set the font style of the bar labels.
Total Bar Color	Set the color of the Total bar.
Subtotal Bar Color	Set the color of the Subtotal bar.
Total Bar Title	Specify the title of the Total bar.

Use increase and decrease color	Color the bars with Increase Color and Decrease Color.
Increase Color	Set the color of the bar when the value increases.
Decrease Color	Set the color of the bar when the value decreases.
Use custom data value color	Customize the color of the labels of the data values.
Positive data value color	Set the color of the positive value labels.
Negative data value color	Set the color of the negative value labels.
Show only top #	Only the top # data are displayed.
Style	Plot discrete or continuous bars on the chart.
Density	Choose the density of the bars.
Group Value Sorting	Sort the group values (from Decrease to Increase, or from Increase to Decrease).
Color	Set the color palette of the data series.
All Data Colors	Allow setting the color for each series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
X-Axis	
Show X-Axis title	Display the title of X-Axis.
X-Axis Title	Specify the title of X-Axis.
Font	Set the font style of X-Axis title.
Show X-Axis title at the end of axis	Display the title at the end of X-Axis.
Show X-Axis labels	Display labels on X-Axis.
Font / Bold	Set the font style of X-Axis labels.
X-Axis Label Rotation	Rotate X-Axis labels.
X-Axis Label Interval	Change the interval between X-Axis labels.
Show X-Axis	Display X-Axis line.
X-Axis Color	Set the color of X-Axis line.
Y-Axis	
Show Y-Axis title	Display the title of Y-Axis.

Y-Axis Title	Specify the title of Y-Axis.
Font	Set the font style of Y-Axis title.
Show Y-Axis title at the end of axis	Display the title at the end of Y-Axis.
Show Y-Axis labels	Display labels on Y-Axis.
Font / Bold	Set the font style of Y-Axis labels.
Show Y-Axis	Display Y-Axis line.
Y-Axis Color	Set the color of Y-Axis line.
Show grid line	Display the grid line of Y-Axis.
Use custom range	Set the range of the grid lines. Enter values in Start and End . The graph drawing beyond this range will be clipped off.
Use custom interval	Change the Interval on Y-Axis.
Tick Interval	Set the interval of the tick marks in axis units.

Tornado Chart

A tornado chart is a special type of bar chart. It is useful for comparing data among different types of data or categories.




Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.

Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Align	Set the vertical or horizontal alignment of the legend.
Label Color	Set the color of the legend labels.
Data	
Show Bar Labels	Display the data labels of the selected series.
Bar Label Contains	Display the data values or/and the percentages on the labels.
Bar Label Position	Set the position of the bar labels.
Bar Label Font	Set the font style of the bar labels.
Use stack	Use stacked bars to show values.
Use 100% stacked	Use 100% stacked bars to show values for hierarchical data. (Each bar height is 100%, and the colored bar segments represent the components' relative contributions to the total bar.)
Stacked Bar Style	Determine how the stacked section is displayed.
Negative Data Bar Background Color	Set the color of the negative data bars.
Minimum Value	Set the minimum value of the bar.
Data Label Color	Set the color of the data labels on the bars.
Use custom data value color	Customize the color of the labels of the data values.
Positive data value color	Set the color of the positive value labels.
Negative data value color	Set the color of the negative value labels.
Show only top #	Only the top # data are displayed.
Style	Plot discrete or continuous bars on the chart.
Density	Choose the density of the bars.
Color	Set the color palette of the data series.
All Data Colors	Allow setting the color for each series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.

Custom	Customize the date and time format .
Y-Axis	
Axis position	Set the position of Y-Axis.
Show Y-Axis title	Display the title of Y-Axis.
Y-Axis Title	Specify the title of Y-Axis.
Font	Set the font style of Y-Axis title.
Fill missing values	Use a continuous axis. The data series are positioned according to their domain value.
Y-Axis Label Interval	Change the interval between Y-Axis labels.
Show Y-Axis labels	Display labels on Y-Axis.
Y-Axis Color	Set the color of Y-Axis line.
X-Axis	
Show X-Axis title	Display the title of X-Axis.
Left X-Axis Title	Specify the title of the left X-Axis.
Right X-Axis Title	Specify the title of the right X-Axis.
Font	Set the font style of X-Axis title.
Show X-Axis title at the end of axis	Display the title at the end of X-Axis.
Show X-Axis labels	Display labels on X-Axis.
Show X-Axis	Display X-Axis line.
X-Axis Color	Set the color of X-Axis line.
Show grid line	Display the grid line of X-Axis.
Use custom range	Set the range of the grid lines. Enter values in Start and End . The graph drawing beyond this range will be clipped off.
Use custom interval	Change the Interval on X-Axis.
Tick Interval	Set the interval of the tick marks in axis units.

Pie / Donut Chart

A pie or donut chart displays data in a series of segments of a circle, with larger segments representing larger data values.

- Pie Chart
- Donut Chart




Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Align	Set the vertical or horizontal alignment of the legend.
Label Color	Set the color of the legend labels.
Data	
Show data labels	Display data labels that clarify the data series.
Show data values	Display the values of the data series.
Show data percentages	Display the data percentages of the slices.
Show label inside slice	Position the slice labels inside the slice. Labels for smaller slices are hidden.
Show label over other slices	All labels are shown. Labels for smaller slices will overlap other slices.
Show slice separator	Add white borders between pie / donut slices.
Data Label Color	Set the color of the data label.
Show only top #	Only the top # data are displayed.

Slice	Group the small slices to a single slice (called Others).
Color	Set the color palette of the data series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
Group	
Show group title	Display the title of the group.
Group Title	Specify the title of the group.
Group Title Font	Set the font style of the group title.

Scatter Chart

A scatter chart plots data with individual data points placed along the X and Y axes.







Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Align	Set the vertical or horizontal alignment of the legend.
Label Color	Set the color of the legend labels.
Data	
Show size values	Display the size of the bubbles.
Density	Choose the density of the data series.
Color	Set the color palette of the data series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
X-Axis	
Show X-Axis title	Display the title of X-Axis.
X-Axis Title	Specify the title of X-Axis.
Font	Set the font style of X-Axis title.
Show X-Axis title at the end of axis	Display the title at the end of X-Axis.
Show X-Axis labels	Display labels on X-Axis.
Font / Bold	Set the font style of X-Axis labels.
X-Axis Label Rotation	Rotate X-Axis labels.

X-Axis Label Interval	Change the interval between X-Axis labels.
Show X-Axis	Display X-Axis line.
X-Axis Color	Set the color of X-Axis line.
Show grid line	Display the grid line of X-Axis.
Use custom range	Set the range of the grid lines. Enter values in Start and End . The graph drawing beyond this range will be clipped off.
Use custom interval	Change the Interval on X-Axis.
Tick Interval	Set the interval of the tick marks in axis units.
Y-Axis	
Show Y-Axis title	Display the title of Y-Axis.
Y-Axis Title	Specify the title of Y-Axis.
Font	Set the font style of Y-Axis title.
Show Y-Axis title at the end of axis	Display the title at the end of Y-Axis.
Show Y-Axis labels	Display labels on Y-Axis.
Font / Bold	Set the font style of Y-Axis labels.
Show Y-Axis	Display Y-Axis line.
Y-Axis Color	Set the color of Y-Axis line.
Show grid line	Display the grid line of Y-Axis.
Use custom range	Set the range of the grid lines. Enter values in Start and End . The graph drawing beyond this range will be clipped off.
Use custom interval	Change the Interval on Y-Axis.
Tick Interval	Set the interval of the tick marks in axis units.
Assistant Line	
	Add an assistant line to the chart to show visual data trends, averages, normal distributions, etc.
	Remove the selected assistant line.
	Rename the selected assistant line.
Value	Select a data series for the assistant line.
Group Value	Select a group value for the assistant line.
Type	Choose the type of assistant line you want.
Show R ² value	Display the R ² value on the chart.
Forward Forecast / Backward Forecast	Specify the number of periods to include in a forecast.
Align with other lines	Align the assistant line with others.
Period	Specify the number of data points used to average the point value.
Smooth	Smooth the angles of the line.
Use custom color	Customize the color of the line.
Line Color	Set the color of the line.
Cap Style	Choose the cap style of the line.
Dash Style	Choose the dash style of the line.

Join Style	Choose the join style of the line.
Visible	Check this box to show the line.

Heatmap

A heatmap represents data in a tabular format as a range of color. A more intense color represents a larger aggregated value for a particular data point.




Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Label Color	Set the color of the legend labels.
Data	
Show data values	Display the values of the data series.

Show data percentages	Display the percentages of the data series.
Font	Set the font style of data labels.
Diverging	Use diverging color scale.
Use custom min/max values	Customize the color of the min, center, and max values. Navicat calculates the cell color based on the color of these values.
Min Color	Set the color of the minimum value in the colormap.
Center Color	Set the color of the value at which to center the colormap.
Max Color	Set the color of the maximum value in the colormap.
Min Value	Specify the minimum value.
Max Value	Specify the maximum value.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
Column	
Show column title	Display the title of the column.
Column Title	Specify the title of the column.
Column Title Font	Set the font style of the column title.
Show column label	Display the column label.
Column Label Color	Set the color of the column label.
Row	
Show row title	Display the title of the row.
Row Title	Specify the title of the row.
Row Title Font	Set the font style of the row title.
Show row label	Display the row label.
Row Label Color	Set the color of the row label.

Treemap

A treemap is an alternative way of visualizing the hierarchical structure while also displaying quantities for each category via area size.




Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Legend	
Show legend	Display the legend container.
Position	Set the position for the legend.
Align	Set the vertical or horizontal alignment of the legend.
Label Color	Set the color of the legend labels.
Data	
Show data point names	Display the names of the data points.
Show data values	Display the values of the data points.
Show data percentages	Display the data percentages of the data points.
Data Label Color	Set the color of the data label.

Tile	Group the small tiles to a single tile (called Others).
Color	Set the color palette of the data points.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .

Value

A value displays a single aggregated value from a data field, e.g. total.

Total

\$259,619.25

Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Data	
Data Label Font	Set the font style of the data label.
Negative Font Color	Set the color of the negative value.
Align	Set the horizontal alignment of the data label.

Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .

Trend

A trend displays that the current value is trending up or down compared to the previous value, and the percentage change.

514.18 
2,523.01 -79.6%

Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Data	
Show previous value	Display the previous value.
Show difference	Display the Value / Percentage difference between the current value and the previous value.
Show indicator	Display the up or down indicator.

Main Label Font	Set the font style of the main label.
Previous Value Color	Set the color of the previous value.
Target Met Color	Set the color of the indicator and the percentage when the value is trending up.
Target Missed Color	Set the color of the indicator and the percentage when the value is trending down.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.

KPI

A KPI displays a comparison between a key value and its target value with a progress bar.




Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.

Data	
Main Label Displayed	Display the Actual value or the Comparison percentage in the main label.
Main Label Font	Set the font style of the main label.
Indicator Thickness	Set the font size of the sub-label on the bar.
Sub Label Color	Set the color of the sub-label on the bar.
Target Caption	Specify the caption of the target label.
Use custom target value	Set the target value.
Target Label Color	Set the color of the target label.
Target Met Color	Set the color of the bar when the value reaches the target.
Target Missed Color	Set the color of the bar when value does not reach the target.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.

Gauge

A gauge is a meter type chart. It has a circular arc and displays a single value which measures the progress toward the target value (the goal).




Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.

Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Data	
Show pointer	Display the needle.
Pipe Width Percentage	Set the percentage that the scale occupies the gauge area.
Background Color	Set the background color of the scale when the needle is not displayed.
Target Color	Set the color of the target line.
Pointer Color	Set the color of the needle.
Value Display	Display the actual data or the comparison percentage of the value.
Value Font	Set the font style of the value.
Target Display	Display the actual data or the comparison percentage of the target value.
Target Caption	Specify the caption of the target label.
Use custom target value	Set the target value.
Target Font	Set the font style of the target value.
Min/Max Displayed	Display the actual data or the comparison percentages of the minimum and maximum values.
Use custom min value	Set the value that the scale starts at.
Use custom max value	Set the value that the scale ends.
Min/Max Font	Set the font style of the minimum and maximum values.
Partition Label Displayed	Display the actual data or the comparison percentages of the partition labels.
Partition Label Font	Set the font style of the partition labels.
Partition (Max. 8)	Divide the scale into number of partitions.
Partition Style	Divide the scale equally or custom the starting percentage of each partition.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.

Table

A table represents data in a tabular view and calculates the total at the end of each column.

Job Title	No. of Employees
AC_ACCOUNT	31
AC_MGR	31
AD_ASST	31
AD_PREST	31
AD_VP	62
FL_ACCOUNT	155
FL_MGR	31
HR_REP	31
IT_PROG	155
MK_MAN	31
MK_REP	31
PR_REP	31
PU_CLERK	155
PU_MAN	31
SA_MAN	155
SA_REP	930
SH_CLERK	620
ST_CLERK	620
ST_MAN	155
	3317.00

Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Data	
Font	Set the font style of the field names and data.
Show alternate row colors	Apply color to alternate rows.
Show vertical grid line	Display the vertical grid line.
Show horizontal grid line	Display the horizontal grid line.
Color	Set the color palette of the data series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.

Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
Databar	
Style	Format the cells by using data bars.
Show bar only item	Only show the data bars in the cells, without the numbers.
Custom min/max values	Customize the min and max values of the data bars.
Min value	Specify the minimum value of the data bar.
Max value	Specify the maximum value of the data bar.
Positive bar color	Set the color of the data bars with positive values.
Negative bar color	Set the color of the data bars with negative values.
Axis color	Set the color of the axis for separating the positive bar and the negative bar.
Total	
Show total	Display totals in the last row of the table.
Total Color	Set the color of the total values.

Pivot Table

A pivot table shows measure values for the intersection of two dimensions and represents data in a tabular view.

Monthly State Sales Report

State	Apr	May	Jun	Jul	Aug	Sep	Oct	Total
BC	\$7,885		\$9,955					17840.00
CA						\$971.70		7259.55
Corfu								766.80
FL		\$2,814.70	\$0	\$32,793	\$10,712			46319.70
GA			\$0		\$18,532			18532.00
HI		\$3,115		\$8,524			\$64,050	91054.00
Jamaica		20,321.75		\$343.80		\$7,807	\$787.80	31070.20
OR		\$5,201	\$0			\$3,632		8833.00
Ontario		\$4,996						4996.00
St. Croix	\$0	\$6,500		\$25,210	\$1,238			32948.00
Total	7885.00	42948.45	9955.00	66870.80	30482.00	12410.70	64837.80	259619.25

Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.

Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Data	
Font	Set the font style of the field names and data.
Show alternate row colors	Apply color to alternate rows.
Show vertical grid line	Display the vertical grid line.
Show horizontal grid line	Display the horizontal grid line.
Color	Set the color palette of the data series.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.
Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .
Databar	
Style	Format the cells by using data bars.
Show bar only item	Only show the data bars in the cells, without the numbers.
Custom min/max values	Customize the min and max values of the data bars.
Min value	Specify the minimum value of the data bar.
Max value	Specify the maximum value of the data bar.
Positive bar color	Set the color of the data bars with positive values.
Negative bar color	Set the color of the data bars with negative values.
Axis color	Set the color of the axis for separating the positive bar and the negative bar.
Total	
Show row total	Display totals in the last row of the table. Enter the name of the row total, and set the color of the values and the background color.
Show column total	Display totals in the last column of the table. Enter the name of the column total, and set the color of the values and the background color.
Show row subtotal	Display totals in the last row of the group. Enter the name of the row subtotal, and set the color of the values and the

	background color.
Show column subtotal	Display totals in the last column of the group. Enter the name of the column subtotal, and set the color of the values and the background color.

Control

A control allows you to filter the data series of all charts in the dashboard that have the same data source during the presentation.

Month

- April
- May
- June
- July
- August
- September
- October
- November
- December
- November

Chart Properties

Once you have selected a chart type, you can customize the chart by changing its properties:

Option	Description
General	
Background Color	Set the background color of the chart area.
Show border	Display the outer chart border.
Border Color	Set the color of the outer chart border.
Show title	Display the chart's main title.
Title	Specify the title of the chart.
Title Font	Set the font style of the title.
Position	Set the position of the title.
Align	Set the vertical or horizontal alignment of the title.
Remarks	Enter remarks for the chart.
Data	
Data Label Color	Set the color of the data label.
Style	Show the data as a list, a range or a combo box.
Data Formats - Number	
Prefix	Add prefix characters to all the numeric data on the chart.
Unit	Choose the unit to shorten the numeric data.
Suffix	Specify the suffix to label the customized unit.

Divider	Specify the divider for the customized unit.
Thousand Separator	Choose the thousands separator for numeric data.
Decimal Separator	Choose the decimal separator for numeric data.
Decimal Places	Specify decimal places for numeric data.
Negatives	Choose the format negative numbers are displayed.
Data Formats - DateTime	
Date / Time	Choose the date and time format of the data.
Custom	Customize the date and time format .

DateTime Formats

The following table shows specifiers you can use to create user-defined data formats for DateTime fields in a chart.


Specifier	Description
D	Display the day as a number without a leading zero (1-31).
DD	Display the day as a number with a leading zero (01-31).
M	Display the month as a number without a leading zero (1-12).
MM	Display the month as a number with a leading zero (01-12).
MMM	Display the month as an abbreviation (Jan-Dec).
MMMM	Display the month as a full month name (January-December).
MMMMM	Display the month as a narrow name (J-D).
YY	Display the year in two-digit numeric format with a leading zero (00-99).
YYYY	Display the year in four-digit numeric format (0000-9999).
h	Display the hour as a number without a leading zero using the 12-hour clock (1-12).
hh	Display the hour as a number with a leading zero using the 12-hour clock (01-12).
H	Display the hour as a number without a leading zero using the 24-hour clock (0-23).
HH	Display the hour as a number with a leading zero using the 24-hour clock (00-23).
m	Display the minute as a number without a leading zero (0-59).
mm	Display the minute as a number with a leading zero (00-59).
S	Display the second as a number without a leading zero (0-59).
SS	Display the second as a number with a leading zero (00-59).
wd	Display the day as a single letter abbreviation (S-S).
Wd	Display the day as an abbreviation (Sun-Sat).
WD	Display the day as a full name (Sunday-Saturday).
w	Display the week of the year (1-52, start of week is Sunday).
WW	Display the week of the year (W01-W52, start of week is Sunday).
q	Display the quarter of the year (1-4).

QQ	Display the quarter of the year (Q1-Q4).
p	Display an uppercase AM with any hour before noon; display an uppercase PM with any hour between noon and 11:59 P.M.

Dashboard

About Dashboard

Dashboard is a collection of charts which allows you to create and view your data visualizations. When you modify a chart, any dashboards containing it will reflect the changes.



① Pages Pane

The Pages pane shows thumbnail images of each page in the dashboard. If the Pages pane is hidden, choose **View -> Show Pages** from the menu bar.

② Dashboard Toolbar

The Dashboard Toolbar provides controls that you can use to refresh the data and present the dashboard.

③ Design Pane

You can design your dashboard on the Design pane. All added objects can be moved (by dragging them with mouse or by keyboard), resized, aligned to the grid, etc.

④ Properties Pane


The **Dashboard Properties** tab includes the basic layout settings. The properties vary with the type of the object.

The **Using** tab shows the charts and data sources that the dashboard depends on.

If the Properties pane is hidden, choose **View -> Show Properties** from the menu bar.

Build Dashboard

The essential steps to create a dashboard are:

1. In the Workspace window, click .
2. Enter the name of the dashboard.
3. Click **OK**.
4. A tab will be opened for your newly created dashboard.
5. Design your dashboard.
6. Select the properties on the right pane which can be further customized for your dashboard.

Note: Each object has different properties.

Hint: You can refresh dashboard to update data in charts with the most current data from their respective data sources.

To manually refresh the dashboard, click .

Working with Grids

Show Grid

To turn the grid on in the dashboard, choose **View** -> **Show Grid** from the menu bar.

Snap to Grid

To align objects on the dashboard with the grid, choose **View** -> **Snap to Grid** from the menu bar.

Add Pages

The Pages pane shows all pages in the dashboard. It displays thumbnails of your dashboard pages.

To add a new page

1. On the Dashboard tab, click the **+** button on the Pages pane.
2. A blank page will be added and selected.

Properties

The available properties of a page:



Option	Description
General	
Dashboard Page Size	Customize the size of pages in the dashboard.
Remarks	Enter remarks for the dashboard.

Page #	
Background	Set the background color of the page. If you choose Image Fill , you can choose the image file and the scaling option.
Opacity	Set the opacity of the image.
Page Note	Enter the reference, comment, or explanation of the page.

Add Charts

Charts provide visual representations of the data in your data source.

To add a chart

1. On the Dashboard tab, click .
2. All available charts in the workspace will be shown as thumbnails. If no charts are available, click  to create one. For detailed instructions on creating charts, see [Build Charts](#).
3. Drag a chart to the Design pane.

Properties


The available properties of a chart:

Option	Description
Position	Customize the position of the chart.
Size	Customize the size of the chart.
Target Charts	Choose which charts in the dashboard the chart can control.
Chart Interaction	
As an interaction control	Set the chart as an interaction control.
Related charts	<p>None - Disable the interaction behavior of the chart.</p> <p>Highlight - Cross-highlight the chart on the dashboard by the selected data point. The unrelated data is still visible but dimmed.</p> <p>Filter - Cross-filter the chart on the dashboard by the selected data point. The unrelated data isn't visible.</p>

Add Text Labels

Text labels are typically used to help document the dashboard, such as adding a dashboard title, URL links.

To add a text label

1. On the Dashboard tab, click .
2. Place it on the dashboard.
3. Enter the caption.

Properties


The available properties of a text label:

Option	Description
Position	Customize the position of the label.
Size	Customize the size of the label.
Caption	Enter the caption of the label.
Horizontal Alignment / Vertical Alignment	Specify the text alignment of the label caption.
Padding	Set the horizontal and vertical padding for the text.
Font	Set the font style of the label caption.
Bold	Apply a bold style to the label caption.
Italic	Apply an italic style to the label caption.
Background Color	Set the background color of the label.
URL	Enter URL path to set the text as a hyperlink.

Add Images

You can insert images (BMP, JPG, JPEG or PNG files) to your dashboard for design or identification purposes.

To add an image

1. On the Dashboard tab, click .
2. Select an image file in the Open dialog box.

Properties

The available properties of an image:

Option	Description
Opacity	Set the opacity of the image.
Position	Customize the position of the image.
Size	Customize the size of the image.
Original Size	Reset the image to its original size.
URL	Enter URL path to set the image as a hyperlink.

Add Shapes

Navicat includes some pre-defined shapes for creating a dashboard: line, arrow, rectangle, ellipse, database, cloud, trigger, server, desktop, mobile, man, woman.

To add a shape

1. On the Dashboard tab, click  and choose a shape type.

2. Place it on the dashboard.

To add a vertex on a line or an arrow

1. Select a line or an arrow on the dashboard.
2. Press and hold the SHIFT key and click on it.

To delete a vertex on a line or an arrow

1. Select a line or an arrow on the dashboard.
2. Press and hold the SHIFT key and click on the vertex.

Properties

The available properties of a shape:

Option	Description
Position	Customize the position of the shape.
Size	Customize the size of the shape. Only for rectangle, ellipse, database, cloud, trigger, server, desktop, mobile, man and woman.
Color	Set the color of the shape.
Show border	Display the outer shape border. Only for rectangle, ellipse, database, cloud, trigger, server, desktop, mobile, man and woman.
Border Color	Change the color of the shape's border. Only for rectangle, ellipse, database, cloud, trigger, server, desktop, mobile, man and woman.
Border Width	Choose the thickness of the border. Only for rectangle, ellipse, database, cloud, trigger, server, desktop, mobile, man and woman.
Line Width	Choose the thickness of the shape.
Cap Style	Choose the cap style of the line/arrow.
Dash Style	Choose the dash style of the line/arrow.
Join Style	Choose the join style of the line/arrow.
Begin Arrow Style	Choose the style of the arrow's back.
End Arrow Style	Choose the style of the arrow's front.

Arrange Objects

You can arrange the objects on a dashboard page in the following ways:

- Move objects forward and backward to layer them.

- Align an object with other objects.
- Distribute the objects horizontally or vertically.
- Group objects to more easily move them as a single unit and synchronize the axis of the related charts.
- Lock objects to prevent them from moving, modifying, or deleting.

Move Objects Forward / Backward

To send an object to the back of the dashboard, control-click it and select **Send to Back**.

To bring an object to the front of the dashboard, control-click it and select **Bring to Front**.

Align Objects

Select multiple objects, then control-click and select **Alignment** -> **Align Left**, **Align Center**, **Align Right**, **Align Top**, **Align Middle** or **Align Bottom**.

Change Objects Distribution

Select multiple objects, then control-click and select **Distribute** -> **Horizontal** or **Vertical**.

Group Objects

Select multiple objects, then click **Group** on the Properties pane and enable the following properties if necessary.

Option	Description
Link Scrolling	Synchronize the scrollbar of all charts.
Link Highlight	Hover over a data point on one of the charts will highlight the same data points on the others.
Show Hints When Highlight	Pop up the hint labels when hovering over a data point on one of the charts.

Ungroup Objects

Select the group, then click **Ungroup** on the Properties pane.


Lock Objects

Select an object, then click **Lock** on the Properties pane.

Unlock Objects

Select the locked object, then click **Unlock** on the Properties pane.

Present Dashboard

You can present the dashboard using the whole screen. The title bar, toolbar, tab bar, Pages pane, Control List and Properties pane will be hidden while in this mode. To open a dashboard in present view, click  **Present**.


Use the arrow keys to navigate between pages.

To exit present view, press the ESC key and the workspace window will be returned to its previous state.

Chart Interaction

All charts on a dashboard with the same data source can be interconnected. If you select a data point on one of the charts, all the other charts on the dashboard page that contain the same data will change based on your selection.



You can turn off chart interaction, or change the behavior to cross-filtering or cross-highlighting in the [dashboard properties](#).



If you have added a [control](#) chart to your dashboard, you can filter the data series of all charts by using the control.

Sort Chart

In the Present mode, you can organize your data in a chart with one click. You can sort data series by a value.

- Hover over a chart until you see the  icon in the upper-right corner.
- Click the  icon to sort on a different value and select the sorting order.

Print & Export Dashboard


Print to a printer

Choose **File** -> **Print** to send your dashboard pages directly to the printer. You can set the printer option in the pop-up window.

Export to a file


Choose **File** -> **Export** and choose the file format to create a PDF, PNG, SVG or JPG file of your dashboard pages.

Switch Theme

Charts and dashboards are not affected by the OS system theme. If you want use a Dark theme for your charts, click  to change the theme.

Chapter 17 - Automation (Available only in Navicat Premium, Enterprise and Standard Edition)

About Automation

Navicat allows you to automate executing jobs at one or more regular intervals. Automation can be created for Query, Backup, Data Transfer, Data Synchronization, Data Generation, Data Dictionary, Aggregation Pipeline, BI, Model, Import, Export, MongoDump, MongolImport, MongoExport, MapReduce. You can define a list of jobs to be performed within one batch job, either run it manually, at the specified time or periodically. In the main window, click  **Automation** to open the automation object list.

Hint: Batch Job files are saved under the default path, e.g. ~/Library/Application Support/PremiumSoft CyberTech/Navicat CC/Navicat Premium/Profiles

Hint: You can run a batch job in Terminal with this command:


```
ProgramPath -batchjob BatchJobName
```

Example: `./"Navicat Premium.app"/Contents/MacOS/"Navicat Premium" -batchjob job1`

Create Batch Job (Step 1)

Add Jobs to Batch Job

In the bottom pane of the **General** tab, select the job type, and then browse the connection, database and/or schema to locate jobs if necessary.



Move selected jobs or all jobs from the **Available Job** list to the **Selected Job** list by clicking or . To delete selected jobs or all jobs from the Selected Jobs list, click or . You are allowed to run profiles from different servers in a single batch job.

To rearrange the sequence of the selected jobs, drag a job to the desired location in the Selected Job list.

If you want to backup whole server, you can select the connection and select **Backup Server xxx**.

You can export BI dashboards or model data dictionaries to PDF files. Adding a BI workspace file to the Selected Jobs list will allow you to choose the export file format and specify the target directory. You can enable the **Append timestamp to file name** option to append timestamp to the name of the exported file.

Exported files can be added to the batch job as mail attachment. Select the job in the Selected Job list and click or to add or remove the mail attachment.

Set Advanced Options & Email Notification

Continue on error

Ignore errors that are encountered during the job execution process.

Send Email

Navicat allows you to generate and send personalized emails with results returned from a schedule. The results can be emailed to multiple recipients.

When

Specify when to send notification emails: the task completed successfully and/or failed.

From

Specify email address of sender. For example, someone@navicat.com.

To, CC

Specify email addresses of each recipient, separating them with a comma or a semicolon (;).

Subject

Specify the email subject with customized format.

Body

Write email content.

Host (SMTP Server)

Enter your Simple Mail Transfer Protocol (SMTP) server for outgoing messages.

Port

Enter the port number you connect to your outgoing email (SMTP) server.

Use authentication

Check this option and enter **Username** and **Password** if your SMTP server requires authorization to send email.

Secure Connection


Specify the connection to use **TLS**, **SSL** secure connection or **Never**.

Send Test Mail

Navicat will send you a test mail indicating success or failure.

Save / Run Batch Job

Before setting schedule, click the  button to save the batch job.

You can run the batch job manually by clicking the  button. The **Message Log** tab displays the execution progress, execution time, and success or failure messages.

Schedule Batch Job (Step 2)

You can click  to set schedule for running a batch job and click  to remove the schedule.

"Hour" and "Minute" fields must be specified. If a field is left without a value, then all the values will be used. For example, if the "Day of the Week" field is empty, then the system will treat the field to be entered with "0, 1, 2, 3, 4, 5, 6".

Use commas to separate values. For example, "0, 1, 3, 6". Use hyphen, without spaces to indicate values. For example, "0-4".

Example: The batch job will be executed at 6:30pm every weekday.

Schedule

Run the Batch Job whenever the clock matches this pattern:

Hour*: 18 0-23

Minute*: 30 0-59

Day of the Week: 1-5 0-6

Day: 1-31

Month: 1-12

? Cancel OK

Note: Please save the batch job before setting schedule. Passwords must be saved in the [Connection](#) window before running your schedule.

Host: 192.168.1.68

Port: 3380

User Name: root

Password: ●●●●●●●●●●

Save password

Chapter 18 - Backup & Restore

About Backup & Restore


A secure and reliable server is closely related to performing regular backups, as failures will probably occur sometimes - caused by attacks, hardware failure, human error, power outages, etc.

Navicat provides backup and restore tools for users to backup/restore database objects.

- [Built-in backup and restore tool](#) for MySQL / PostgreSQL / SQLite / MariaDB
- [Oracle Data Pump](#)
- [SQL Server Backup & Restore](#)
- [MongoDump & MongoRestore](#)
- [Built-in backup and restore tool](#) for Redis

MySQL / PostgreSQL / SQLite / MariaDB (Available only in Navicat Premium, Enterprise and Standard Edition)

About Built-in Backup & Restore Tool

The built-in backup & restore tool allows you to backup/restore database objects for your database. You can save your settings as a profile for future use or setting [automation tasks](#). In the main window, click  **Backup** to open the backup object list.

Hint: Backup files are saved under the [Settings Location](#). To open the folder, control-click a backup file and select **Show in Finder**.

Note: Available only for MySQL, PostgreSQL, SQLite and MariaDB.

Backup

General Properties

In this tab, you can view the server and database information. Enter a comment for the backup file if necessary.

Object Selection

In this tab, choose database objects you wish to backup.

(*)	All the database objects being backed up, all newly added database objects will also be backed up without amending the backup profile.
(#/#)	Only the checked database objects will be backed up. However, if

	you add any new database objects in the database and/or schema after you create your backup profile, the newly added database objects will not be backed up unless you manually modify the Objects list.
--	--

Advanced Properties

Note: The following options depend on the connection server type and sort in ascending order.

Lock all tables

Lock all objects while backup is being processed.

Use single transaction (InnoDB only)

If a table uses InnoDB storage engine, with this option is on, Navicat uses transaction before the backup process starts.


Use specified file name

Define your file name for backup. Otherwise, your backup file will be named with "YYYYMMDDhhmmss" format.

Restore

Restore feature will firstly drop the selected objects of the database, then recreate the new objects according to your backup. Finally, inserting the data.

Restore a backup to an existing database/schema

1. In the main window, open a database/schema.
2. Click **Backup** and select an existing backup file.
3. Click  from the object toolbar.
4. Choose the restore options and click **Start**.

Restore a backup to a new database/schema

1. Create and open a new database/schema.
2. Click **Backup**.
3. In the Objects tab, control-click anywhere and select **Restore Backup from**.
4. Browse the backup file.
5. Choose the restore options and click **Start**.

Hint: You can also restore Navicat Windows and Linux backups.

Note: You must have Create, Drop and Insert privileges ([MySQL/MariaDB](#) or [PostgreSQL](#)) to run the restore.

General Properties

In this tab, you can view the target server and database information and the backup file information.

Object Selection

In this tab, choose database objects you wish to restore.

Advanced Properties

Note: The following options depend on the connection server type, the backup file version and sort in ascending order.

Continue on error

Ignore errors that are encountered during the restore process.

Create indexes

Create indexes for the restored table with this option is on.

Create tables

Create tables during the restore process with this option is on.

Create records

Restore table records with this option is on. Otherwise, only table structures will be restored.

Create triggers

Create triggers for the restored table with this option is on.

Empty table

Delete all table records in the database/schema.

Lock tables for write

Lock the tables to prevent user to modify tables during the restore process.

Overwrite existing events

Overwrite if events already exist in the database/schema.

Overwrite existing functions

Overwrite if functions already exist in the database/schema.

Overwrite existing indexes

Overwrite if indexes already exist in the database/schema.

Overwrite existing sequences

Overwrite if sequences already exist in the database/schema.

Overwrite existing tables

Overwrite if tables already exist in the database/schema.

Overwrite existing triggers

Overwrite if triggers already exist in the database/schema.

Overwrite existing types

Overwrite if types already exist in the database/schema.

Overwrite existing views

Overwrite if views already exist in the database/schema.

Use extended insert statements

Check this option if you want to insert records using extended insert syntax.

Example: `INSERT INTO `users` VALUES ('1', 'Peter McKindsy', '23'), ('2', 'Johnson Ryne', '56'), ('0', 'Katherine', '23');`


Use transaction

Check this option if you want to rollback all data when error occurs.

Extract SQL

Extract SQL allows extracting SQL into a SQL file from your backup file.

Extract a backup file that is in your database/schema

1. Open a database/schema.
2. Click **Backup** and select an existing backup file.
3. Click  from the object toolbar.
4. Choose the [Extract SQL options](#) and click **Start**.
5. Choose a path for the SQL file.


Extract a backup file that is in any location

1. Open any one of your databases/schemas.

2. Click **Backup**.
3. In the Objects tab, control-click anywhere and select **Extract SQL from**.
4. Browse the backup file.
5. Choose the [Extract SQL options](#) and click **Start**.
6. Choose a path for the SQL file.

Oracle Data Pump (Available only in Navicat Premium, Enterprise and Standard Edition)

About Oracle Data Pump

Data Pump includes two utilities: Data Pump Export and Data Pump Import. Data Pump Export is for unloading data and metadata into a dump file set. Data Pump Import is for loading an export dump file set into a target system. In the main window, click  **Data Pump** to open the data dump object list.

To change the directory of the dump file set, control-click anywhere in the Objects tab and select **Change Directory**.

Note: Data Pump is added in Oracle 10g or later. You require SYSDBA role to perform it. Dump file sets are stored in servers.

Oracle Data Pump Export

Before executing Data Pump Export, select the **SQL Preview** tab to review the SQL statements. Then, you can click the **Start** button to run the export process.

You can save the Data Pump Export settings to a profile for future use. Data Pump Export profiles (.nbakora) are saved under the [Settings Location](#).

To show the hidden tabs (advanced options), check the **Show Advanced Options** option.

General Properties

Job Name

Specify the name of the job.

Mode

Choose the export mode: FULL, TABLESPACE, SCHEMAS, TABLE.

Content

Choose which data to export.

Export Data

Select which objects to export. If you select the TABLE export mode, choose a schema in the **Schema** drop-down menu.

Dump Files

Add dump files to the dump file set for the export.

Metadata Filter

In this tab, you can include or exclude specific objects types.

Data Filter

Query

Specify a subquery that is added to the end of the SELECT statement for a table.

Sample

Specify a percentage for sampling the data blocks to be moved.

Remap Data

In this tab, you can specify remap functions for column data.

Encryption

Encryption Content

Choose what to encrypt in the dump file set.

Encryption Algorithm

Choose a cryptographic algorithm to perform encryption.

Encryption Mode

Choose the encryption mode: Transparent, Encryption Password, Dual.

Encryption Password

If you choose the Encryption Password or Dual encryption mode, enter a password to encrypt data written to the dump file.

Confirm Password

Re-type your password.

Advanced Properties

Thread Number

Enter the maximum number of worker processes that can be used for the job.

Reuse file

Check this option to overwrite a preexisting file.

Enable XMLCLOBS

Check this option to enable data options for XMLCLOBS.

Enable cluster

Check this option to start workers on instances usable by the job.

Service Name

Specify a service name that used to constrain the job to specific instances or to a specific resource group.

Version

Specify the version of database objects to be extracted.

Database Link

Choose a database link to the remote database that will be the source of data and metadata for the job.

Estimate

Choose the estimate method for the size of the tables should be performed before starting the job.

Compression Type

Specify which data to compress before writing to the dump file set.

Transportable

If you select the TABLE export mode, choose to never or always use the transportable option.

Access Method

Choose an alternative method to unload data if the default method does not work.

Source Edition

Specify the application edition.

Directory

Choose the directory for saving the log file.

Log File Name

Enter the name of the log file.

Flashback SCN

Enter the system change number (SCN) that used to enable the Flashback Query utility.

Flashback Time

Select a timestamp for finding a SCN.

Oracle Data Pump Import

Before executing Data Pump Import, select the **SQL Preview** tab to review the SQL statements. Then, you can click the **Start** button to run the import process.

To show the hidden tabs (advanced options), check the **Show Advanced Options** option.

General Properties

Job Name

Specify the name of the job.

Mode

Choose the import mode: FULL, TABLESPACE, SCHEMAS, TABLE.

Content

Choose which data to import.

Table Exists Action

Specify the action to be performed when data are loaded into a preexisting table.

Import Data

Select which objects to import. If you select the TABLE import mode, specify the schema name in the **Schema** text box.

Dump Files

Add dump files to the dump file set for the import.

Network

Database Link

Choose a database link to the remote database that will be the source of data and metadata for the job.

Estimate

Choose the estimate method for the size of the tables should be performed before starting the job.

Flashback SCN

Enter the system change number (SCN) that used to enable the Flashback Query utility.

Flashback Time

Select a timestamp for finding a SCN.

Transportable

If you select the TABLE export mode, choose to never or always use the transportable option.

Datafile Path

Specify the full file specification for a datafile in the transportable tablespace set.

Filters

Include/Exclude

Include or exclude specific objects types.

Query

Specify a subquery that is added to the end of the SELECT statement for a table.

Remap Data

Remap Data

Specify remap functions for column data.

Remap DataFiles

Specify the remapping for data files.

Remap Objects

Remap Schemas

Specify the remapping for schemas.

Remap Tablespaces

Specify the remapping for tablespaces.

Remap Tables

Specify remap functions for tables.

Advanced Properties

Number of worker processes to be used

Enter the maximum number of worker processes that can be used for the job.

Reuse datafiles

Check this option to reuse existing data files for creating tablespace.

Skip unusable indexes

Check this option to skip loading tables that have indexes that were set to the Index Unusable state.

Skip const error

Check this option to skip constraint violations and continue the load.

Disable append hint

Check this option to prevent the append hint from being applied to the data load.

Cluster

Check this option to start workers on instances usable by the job.

Service Name

Specify a service name that used to constrain the job to specific instances or to a specific resource group.

Version

Specify the version of database objects to be extracted.

Streams configuration

Check this option to import any general Streams metadata that may be present in the export dump file

Partition Options

Choose how to handle partitioned tables during the import operation.

Access Method

Choose an alternative method to unload data if the default method does not work.

Encryption Password

Enter the password if an encryption password was specified in Data Pump Export.

Target Edition

Specify the database edition into which objects should be imported.

Segment Attributes, Segment Creation, Storage, OID, PCTSpace

Choose the objects that the transformations to be applied to.

Directory


Choose the directory for saving the log file.

Log File Name

Enter the name of the log file.

SQL Server Backup & Restore (Available only in Navicat Premium, Enterprise and Standard Edition)

About SQL Server Backup & Restore

The **SQL Server Backup** feature provides an important safeguard for protecting your SQL Server data. In the main window, click  **SQL Server Backup** to open the backup object list.

If you want to backup with the setting of an existing backup file, you can control-click a backup file in the Objects tab and select **Backup From This Setting**.

Note: Backup files are stored in servers.

If you want to restore from a backup file that is not listed in the Objects tab, you can control-click anywhere in the Objects tab and select **Restore From File**.

SQL Server Backup

Before starting the backup process, click the **Generate SQL** button to review the SQL statements. Then, you can click the **Start** button to run the backup process.

You can save the backup settings to a profile for future use. Backup profiles (.nbakmssql) are saved under the [Settings Location](#).

To show the hidden tabs (advanced options), check the **Show Advanced Options** option.

General Properties

Backup Set Name

Specify the name of the backup set.

Description

Specify the description of the backup set.

Backup Type

Choose the type of the backup that you want to perform: Full Backup, Differential Backup, Transaction-Log Backup.

Copy-only

Check this option to specify that the backup is a copy-only backup.

New media set

Create a new media set for this backup. To add backup devices or files to the list, click the **Add device** button.

Existing media set

Choose an existing media set for the backup.

Components

In this tab, you can choose to backup the whole database, the partial database, or specific files or groups.

Advanced Properties

Never expire

Specify the backup set never expires.

Expire after

Specify the number of days that must elapse before this backup media set can be overwritten.

Expire on

Specify when the backup set expires and can be overwritten.

Password

Enter a password for the backup set.

Format media set

Check this option to specify that a new media set be created.

New Name

Enter the name of the new media set.

Description

Specify the description of the media set.

Overwrite all backups

Check this option to specify that all backup sets should be overwritten, but preserves the media header.

Check media name and backup set expiration

Check this option to check the expiration date and time of the backup sets on the media before overwriting them.

Media Set Name

Specify the media name for the entire backup media set.

Password

Enter a password for the media set.

Truncate the transaction log

Choose this option to truncate the transaction log.

Back up the tail of the log and leave the database in the restoring state

Choose this option to back up the tail of the log and leaves the database in the RESTORING state.

Verify backup

Check this option to verify the backup.

Perform checksum

Check this option to enable the backup checksums.

Continue on error

Ignore errors (such as invalid checksums or torn pages) that are encountered during this backup.

Compression

Choose whether backup compression is performed on this backup.

SQL Server Restore

Before starting the restore process, click the **Generate SQL** button to review the SQL statements. Then, you can click the **Start** button to run the restore process.

General Properties

Restore to database

Select a database to restore.

Source of backup set

If you chose **Restore From File** in the Objects tab, you can add backup devices or files to the list by clicking the **Add device** button.

Latest possible

Choose this option if do not have the restore point.

Specific time

Choose this option to specify that the database be restored to the state it was in as of the date and time.

Marked transaction

Choose this option to recover to a specified recovery point.

Include marked transaction

Check this option to include the specified transaction in the recovery.

Restore plan

If you chose **Restore From File** in the Objects tab, you can choose the database backup files from the list.

Advanced Properties

Restore database files to

Specify that the data or log file should be moved by restoring it to the **Restore To** location.

WITH REPLACE

Check this option to include the WITH REPLACE argument.

WITH RESTRICTED_USER

Check this option to include the WITH RESTRICTED_USER argument.

WITH KEEP_REPLICATION

Check this option to include the WITH KEEP_REPLICATION argument.

RECOVERY

Choose this option to roll back all uncommitted transactions.

NORECOVERY

Choose this option to not roll back the uncommitted transactions.

STANDBY

Specify a **Standby file** that allows the recovery effects to be undone.

MongoDump & MongoRestore

About MongoDump & MongoRestore

MongoDB provides two utilities for backup and restore operations: MongoDump and MongoRestore. They are useful for creating backups of small database and restoring data.

MongoDump

MongoDump can read data from a MongoDB database and create high fidelity BSON files.

Note: You must have [mongodump](#) executable for this feature to work.

To dump a file

1. In Navicat main window, control-click your database or collection and select **MongoDump**.
2. In the **General** and **Advanced** tabs, select the output path and the appropriate dump options.
3. Click the **Start** button to begin the dump process. The **Message Log** tab will display the dump progress, execution time, and success or failure messages.

You can save your settings as a profile for future use or setting [automation tasks](#). To open a saved profile, click the **Load Profile** button and select a profile from the list.

Hint: Profiles are saved under the default path, e.g. ~/Library/Application Support/PremiumSoft CyberTech/Navicat CC/Common/Profiles

MongoRestore

MongoRestore can load data from a binary database dump created by MongoDump into a MongoDB database.

Note: You must have [mongorestore](#) executable for this feature to work.

To restore database

1. In Navicat main window, control-click your database and select **MongoRestore**.
2. In the **General** and **Advanced** tabs, select the input file/directory path and the appropriate restore options.


3. Click the **Start** button to begin the restore process. The **Message Log** tab will display the restore progress, execution time, and success or failure messages.

You can save your settings as a profile for future use. To open a saved profile, click the **Load Profile** button and select a profile from the list.

Hint: Profiles are saved under the default path, e.g. ~/Library/Application Support/PremiumSoft CyberTech/Navicat CC/Common/Profiles

Redis (Available only in Navicat Premium, Enterprise and Standard Edition)

About Built-in Backup & Restore Tool

The built-in backup & restore tool allows you to backup/restore database objects for your database. You can save your settings as a profile for future use or setting [automation tasks](#). In the main window, click  **Backup** to open the backup object list.

Hint: Backup files are saved under the [Settings Location](#). To open the folder, control-click a backup file and select **Show in Finder**.

Note: Available only for Redis.

Backup

General Properties

In this tab, you can view the server and database information. Enter a comment for the backup file if necessary.

Options

Key Pattern

Enter a key pattern. Navicat only backs up keys that match the specified pattern.

Data Types

Choose the type of data to back up.

Include volatile keys

Include keys with timeout expiration set.

Store TTL information

Back up the Time-to-Live (TTL) information of volatile keys.

Use specified file name

Define your file name for backup. Otherwise, your backup file will be named with "yyyymmddhhmmss" format.

Restore

Restore feature will firstly delete the keys in the selected namespaces, then recreate the keys.

Restore a backup to an existing database

1. In the main window, open a database.
2. Click **Backup** and select an existing backup file.
3. Click **Restore Backup** from the object toolbar.
4. Choose the restore options and click **Start**.

Restore a backup to another database

1. Open another database.
2. Click **Backup**.
3. In the Objects tab, control-click anywhere and select **Restore Backup from**.
4. Browse the backup file.
5. Choose the restore options and click **Start**.

Hint: You can also restore Navicat Windows and Linux backups.

General Properties

In this tab, you can view the target server and database information and the backup file information.

Details

In this tab, you can view the backup settings and summary.

Namespace Selection

In this tab, choose namespaces you wish to restore.

Advanced Properties

Data Types

Choose the type of data to restore.

Include persistent keys

Include keys that will never expire.

Include volatile keys

Include keys with timeout expiration set.

Include TTL information

Restore the Time-to-Live (TTL) information of volatile keys. You can choose to restore the remaining TTL, the original expiration time or a custom TTL.

Delete key before restoring if key exists

If keys already exist in the target database, the existing keys will be deleted once the restore process starts.

Delete all keys of the target database before restoring

Delete all keys in the target database once the restore process starts.

Delete asynchronously

Delete keys from the server asynchronously. The operation will be executed in a background thread.

Disable replies from server

Stop the server from replying to commands.


Continue on error

Ignore errors that are encountered during the restore process.

Extract Command

Extract Command allows extracting commands into a Redis command file from your backup file.

Extract a backup file that is in your database

1. Open a database.
2. Click **Backup** and select an existing backup file.
3. Click  from the object toolbar.
4. Choose the [Extract Command options](#) and click **Start**.
5. Choose a path for the command file.


Extract a backup file that is in any location

1. Open any one of your databases.

2. Click **Backup**.
3. In the Objects tab, control-click anywhere and select **Extract Command from**.
4. Browse the backup file.
5. Choose the [Extract Command options](#) and click **Start**.
6. Choose a path for the command file.

Chapter 19 - Server Security

About Server Security

Navicat provides a powerful tool for you to manage server user accounts and the privileges of database objects. All information of users and privileges are stored in the server. In the main window, click  **User** to open the user/role object list.

MySQL / MariaDB User & Role Management

User Designer

General Properties

User Name

Define a name for the user account.

Host

Enter a host name or an IP address where the user connected from. % means any host.

Plugin

Select the account authentication plugin for the user.

Password

Specify a login password for the user.

Confirm Password

Re-type the login password.

Expire Password Policy

Select the password expiration policy for the user account.

Member Of

Note: Roles are available for MySQL 8.0 or later or MariaDB 10.0.5 or later.

In the grid, check the **Granted** or **Default** option against the role listed in **Name** to assign this user to be a member of the selected role.

Advanced Properties

Maximum Queries Per Hour, Maximum Updates Per Hour, Maximum Connections Per Hour

Specify the maximum number of queries, updates, and connections that a user can perform during any given one-hour period. 0 means no limit.

Maximum User Connection

Specify the maximum number of simultaneous connections that a user can make.

Use OLD_PASSWORD encryption

Use the OLD_PASSWORD() function to generate a hash value for storing user password.

SSL Type

Specify the SSL/TLS-related options for the user account.

ANY	Require SSL encryption when the user connects.
SPECIFIED	Require a valid certificate when the user connects. Provide SSL Cipher , Certificate Issuer , or Certificate Subject .
X509	Require a valid certificate when the user connects.

Server Privileges

In the grid, check the **Grant** option against the server privilege listed in **Privilege** to assign this user to have that privilege. To grant or revoke all privileges, control-click on the grid and select **Grant All** or **Revoke All**.

Object Privileges

To edit specific object privileges for the user, click  to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Grant** option against the privilege listed in **Privilege** to assign this user to have that privilege. To grant or revoke all privileges, control-click on the grid and select **Grant All** or **Revoke All**.

Role Designer

Note: Roles are available for MySQL 8.0 or later or MariaDB 10.0.5 or later.

General Properties

Role Name

Define a name for the role.

Members

In the grid, check the **Granted** option against the role/user listed in **Name** to assign the selected role/user to be a member of this role.

Member Of

In the grid, check the **Granted** option against the role listed in **Name** to assign this role to be a member of the selected role.

Server Privileges

In the grid, check the **Grant** option against the server privilege listed in **Privilege** to assign this role to have that privilege. To grant or revoke all privileges, control-click on the grid and select **Grant All** or **Revoke All**.

Object Privileges

To edit specific object privileges for the role, click  to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Grant** option against the privilege listed in **Privilege** to assign this role to have that privilege. To grant or revoke all privileges, control-click on the grid and select **Grant All** or **Revoke All**.

Oracle User & Role Management

User Designer

General Properties

User Name

Define a name for the user.

Authentication

Select the authentication method.

PASSWORD	Create a user. Specify a Password and re-type it in Confirm Password . Check the Expire Password option to force the user to change the password on the first attempted login.
EXTERNAL	Create a user authorised by an external service. Enter the certificate distinguished name or the Kerberos principal name in External Name .
GLOBAL	Create a user authorised by the enterprise directory service. Enter the X.509 name at the enterprise directory service that identifies the user in X.500 Distinguished Name .

Default Tablespace

Choose the default tablespace for objects that the user creates.

Temporary Tablespace

Choose the tablespace or tablespace group for the user's temporary segments.

Profile

Choose the profile that assign to the user.

Locked Account

Lock the user's account and disable access.

Enable Editions

Allow the user to create multiple versions of editionable objects in this schema.

Roles

In the grid, check the **Grant**, **Admin Option** or **Default** option against the role listed in **Role Name** to assign this user to be a member of the selected role.

Quotas

In the grid, specify the maximum amount of space that the user can allocate in the tablespaces. Enter the **Quota** and choose the **Unit**. **Unlimited** lets the user allocate space in the tablespace without bound. Multiple tablespaces can be set.

Server Privileges

In the grid, check the **Grant** or **Admin Option** option against the server privilege listed in **Privilege** to assign this user to have that privilege. To grant or revoke all privileges, control-click on the grid and select **Grant All**, **Grant All With Admin Option** or **Revoke All**.

Object Privileges

To edit specific object privileges for the user, click  to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Grant** or **Grant Option** option against the privilege listed in **Privilege** to assign this user to have that privilege. To grant or revoke all privileges, control-click on the grid and select **Grant All**, **Grant All With Grant Option** or **Revoke All**.

Role Designer

General Properties

Role Name

Define a name for the role.

Authentication

Select the authentication method.

PASSWORD	Create a role. Specify a Password and re-type it in Confirm Password .
EXTERNAL	Create a role authorised by an external service.
GLOBAL	Create a role authorised by the enterprise directory service.
NOT IDENTIFIED	Create a role without a password.

Roles

In the grid, check the **Granted** or **Admin Option** option against the role listed in **Role Name** to assign this role to be a member of the selected role.

Members

In the grid, check the **Granted** or **Admin Option** option against the user listed in **Name** to assign the selected user to be a member of this role.

Server Privileges

In the grid, check the **Grant** or **Admin Option** option against the server privilege listed in **Privilege** to assign this role to have that privilege. To grant or revoke all privileges, control-click on the grid and select **Grant All**, **Grant All With Admin Option** or **Revoke All**.

Object Privileges

To edit specific object privileges for the role, click  to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Granted** option against the privilege listed in **Privilege** to assign this role to have that privilege. To grant or revoke all privileges, control-click on the grid and select **Grant All** or **Revoke All**.

Maintain User

Navicat provides a complete solution for maintaining Oracle users.

1. In the main window, select users in the Objects tab.

- Control-click the selected users.
- Choose **Maintain**, and then choose a maintain option the from the pop-up menu.

Option	Description
Lock User	Lock the user account and disable access.
Unlock User	Unlock the user account and enable access.
Expire User	Set the password of the user account to expire.

PostgreSQL User, Group & Role Management

User Designer

Note: Users are available for PostgreSQL 8.0 or below.

General Properties

User Name

Define a name for the user.

User ID

Specify an ID for the user.

Password

Specify a login password for the user.

Confirm Password

Re-type the login password.

Password Encryption

Choose whether the password is stored ENCRYPTED or UNENCRYPTED in the system catalogs.

Expiry Date

Set a datetime that the user's password will expire. If this option is omitted, the password will be valid for all time.

Superuser

Check this option to determine the user is a superuser.

Can create databases

Check this option to allow the user to create databases.

Members Of

In the grid, check the **Granted** option against the group listed in **Group Name** to assign this user to be a member of the selected group.

Object Privileges

To edit specific object privileges for the user, click  to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Granted** or **Grant Option** option against the privilege listed in **Privilege** to assign this user to have that privilege. To grant or revoke all privileges, control-click on the grid and select **Grant All**, **Grant All With Grant Option** or **Revoke All**.

Group Designer

Note: Groups are available for PostgreSQL 8.0 or below.

General Properties

Group Name

Define a name for the group.

Group ID

Specify an ID for the group.

Members

In the grid, check the **Granted** option against the user listed in **Member** to assign the selected user to be a member of this group.

Object Privileges

To edit specific object privileges for the group, click  to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Granted** option against the privilege listed in **Privilege** to assign this group to have that privilege. To grant or revoke all privileges, control-click on the grid and select **Grant All** or **Revoke All**.

Role Designer

Note: Roles are available for PostgreSQL 8.1 or later.

General Properties

Role Name

Define a name for the role.

Role ID

Specify an ID for the role.

Can Login

Check this option to allow the role to log in.

Password

Specify a login password for the role.

Confirm Password

Re-type the login password.

Password Encryption

Choose whether the password is stored ENCRYPTED or UNENCRYPTED in the system catalogs.

Connection Limit

Specify how many concurrent connections the role can make. -1 means no limit.

Expiry Date

Set a datetime that the role's password will expire. If this option is omitted, the password will be valid for all time.

Can create databases

Check this option to allow the role to create databases.

Superuser

Check this option to determine the role is a superuser.

Can modify catalog directly

Check this option to allow the role to update system catalog.

Inherits rights from parent roles

Check this option to determine the role inherits the privileges of roles it is a member of.

Can create roles

Check this option to allow the role to create roles.

Can replicate

Check this option to allow the role to initiate streaming replication or put the system in and out of backup mode.

Can bypass RLS

Check this option to allow the role to bypasses every row-level security (RLS) policy.

Members

In the grid, check the **Granted** or **Admin Option** option against the role listed in **Member** to assign the selected role to be a member of this role.

Members Of

In the grid, check the **Granted** or **Admin Option** option against the role listed in **Role Name** to assign this role to be a member of the selected role.

Object Privileges

To edit specific object privileges for the role, click  to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Granted** or **Grant Option** option against the privilege listed in **Privilege** to assign this role to have that privilege. To grant or revoke all privileges, control-click on the grid and select **Grant All**, **Grant All With Grant Option** or **Revoke All**.

SQL Server Login, Role & User Management

Login Designer

Note: The following options and tabs depend on the server version and the authentication type.

General Properties

User Name

Define a name for the login.

Authentication Type

Select the authentication type of the login.

Password

Specify a password for the login.

Confirm Password

Re-type the login password.

Specify Old Password

Check this option to enter the old password used by this account when editing the login.

Enforce password policy

Check this option to force password to follow password policy of SQL Server.

Enforce password expiration

Check this option to force password to have expiry date.

User must change password at next login

Check this option to force user to change password every time when login.

Default Database

Select the default database when login.

Default Language

Select the default display language when login.

Certificate Name

Select the certificate to be used for the login.

Asymmetric Key Name

Select the asymmetric key to be used for the login.

Credential

Select the credentials to be mapped to the login.

Enabled

Check this option to enable the login.

User Mappings

In the grid, check the **Database** and enter the **User** and **Default Schema** to create user for login the database and specify the first schema will be searched by the server.

Roles

In the list, assign this server login to be a member of the selected server role.

Server Permissions

In the grid, check the **Grant**, **Grant Option** or **Deny** option against the server permissions listed in **Privileges** to assign this login to have that permission. To grant, deny or revoke all permissions, control-click on the grid and select **Grant All**, **Grant All With Admin Option**, **Deny All** or **Revoke All**.

Login Permissions

In the grid, check the permissions against the endpoint listed in **Login** to assign this login to have that login permission. Click the checkbox twice to grant the permission with Grant Option. Click the checkbox three times to deny the permission.

Endpoint Permissions

In the grid, check the permissions against the endpoint listed in **Endpoint** to assign this login to have that endpoint permission. Click the checkbox twice to grant the permission with Grant Option. Click the checkbox three times to deny the permission.

Server Role Designer

Note: Azure SQL Database does not support Server Role.

In the **Members** tab, assign the selected login to be a member of this server role.

Database User Designer

Note: The following options and tabs depend on the server version and the user type.

General Properties

User Name

Define a name for the database user.

Authentication

Select the security type for database user.

User Name

Assign a SQL Server login that the database user uses.

Default Schema

Select the default schema that will own objects created by the database user.

Certificate Name

Select the certificate to be used for the database user.

Asymmetric Key Name

Select the asymmetric key to be used for the database user.

Roles

In the list, assign this database user to be a member of the selected database role.


Owned Schemas

In the list, check the schemas that are owned by the database user.

Database Permissions

In the grid, check the **Grant**, **Grant Option** or **Deny** option against the database permissions listed in **Privilege** to assign this database user to have that permission. To grant, deny or revoke all permissions, control-click on the grid and select **Grant All**, **Grant All With Admin Option**, **Deny All** or **Revoke All**.

Object Privileges

To edit specific object permissions for the database user, click  to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Grant**, **Grant Option** or **Deny** option against the permission listed in **Privilege** to assign this database user to have that permission. To grant, deny or revoke all permissions, control-click on the grid and select **Grant All**, **Grant All With Grant Option**, **Deny All** or **Revoke All**.

Database Role Designer

Note: The following options and tabs depend on the server version.

General Properties

Role Name

Define a name for the database role.

Owner

Assign the owner for the database role.

Members

In the list, assign the selected database users and roles to be a member of this database role.

Members Of

In the list, assign this database role to be a member of the selected database roles.


Owned Schemas

In the list, check the schemas that are owned by the database role.

Database Permissions

In the grid, check the **Grant**, **Grant Option** or **Deny** option against the database permissions listed in **Privilege** to assign this database role to have that permission. To grant, deny or revoke all permissions, control-click on the grid and select **Grant All**, **Grant All With Admin Option**, **Deny All** or **Revoke All**.

Object Privileges

To edit specific object permissions for the database role, click  to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Grant**, **Grant Option** or **Deny** option against the permission listed in **Privilege** to assign this database role to have that permission. To grant, deny or revoke all permissions, control-click on the grid and select **Grant All**, **Grant All With Grant Option**, **Deny All** or **Revoke All**.

Application Role Designer

Note: Azure SQL Database does not support Application Role. The following options and tabs depend on the server version.

General Properties

Role Name

Define a name for the application role.

Password

Specify a password for the application role.

Confirm Password

Re-type the password.

Default Schema

Select the default schema that will own objects created by the application role.


Owned Schemas

In the list, check the schemas that are owned by the application role.

Database Permissions

In the grid, check the **Grant**, **Grant Option** or **Deny** option against the database permissions listed in **Privilege** to assign this application role to have that permission. To grant, deny or revoke all permissions, control-click on the grid and select **Grant All**, **Grant All With Admin Option**, **Deny All** or **Revoke All**.

Object Privileges

To edit specific object permissions for the application role, click  to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the object to show the grid on the right pane.
3. In the grid, check the **Grant**, **Grant Option** or **Deny** option against the permission listed in **Privilege** to assign this application role to have that permission. To grant, deny or revoke all permissions, control-click on the grid and select **Grant All**, **Grant All With Grant Option**, **Deny All** or **Revoke All**.

SQLite User Management

Note: By default, a SQLite database does not require user authentication (no-authentication-required database). After you created a user, the database will be marked as requiring authentication (authentication- required database). Then, user need to provide username and password when connecting to the database file.

General Properties

User Name

Define a name for the user account.

Password

Specify a login password for the user.

Confirm Password

Re-type the login password.

Administrator

Check this option to give the admin privilege to the user.

MongoDB User & Role Management

User Designer

General Properties

User Name

Define a name for the user.

Password

Specify a login password for the user.

Confirm Password

Re-type the login password.

Password Digestor

Indicate whether the server or the client digests the password.

Mechanisms

Specify the SCRAM mechanisms for creating SCRAM user credentials.

Custom Data

In this tab, you can enter any information associated with this user.

Built-in Roles

In the list, assign this user to be a member of the selected built-in role.

User-defined Roles

In the list, assign this user to be a member of the selected user-defined role.

Authentication Restrictions

To edit specific authentication restrictions that the server enforces on the user, click .

Client Source

Specify a list of IP addresses or CIDR ranges to restrict the client's IP address.

Server Address

Specify a list of IP addresses or CIDR ranges to which the client can connect.

Role Designer

General Properties

Role Name

Define a name for the role.

Built-in Roles

In the list, assign this role to be a member of the selected built-in role.

User-defined Roles

In the list, assign this role to be a member of the selected user-defined role.


Members (Roles)

In the list, assign the selected role to be a member of this role.

Members (Users)

In the list, assign the selected user to be a member of this role.

Authentication Restrictions

To edit specific authentication restrictions that the server enforces on the role, click .

Client Source

Specify a list of IP addresses or CIDR ranges to restrict the client's IP address.

Server Address

Specify a list of IP addresses or CIDR ranges to which the client can connect.

Privileges

To edit specific object privileges for the role, click  to open the window and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Check the objects that you want to grant the privileges on.
3. In the grid, check the **State** option against the privilege listed in **Privilege** to assign this role to have that privilege. To grant or revoke all privileges, control-click on the grid and select **Grant All** or **Revoke All**.

Redis User Management

You can define users in Redis Access Control Lists (ACLs) to protect access to your data. Navicat provides a graphical interface for you to create, edit and delete users.

Note: Users are available for Redis 6 or later.

General Properties

User Name

Define a name for the user account.

Can login

Enable the user account.


Require Password

Require the user to log in with a password.


Add Password

Add a password or a SHA-256 hash value to the list of valid passwords for the user.


Privileges

You can create new privilege groups (selectors) to add multiple sets of rules to the user. New privilege groups are evaluated after the main privilege group, and are evaluated according to the order they are defined. Click  **Add Privilege Group / Add Privilege Groups with Batch**.

Commands

To allow and disallow commands, click  **Add Command / Add Commands with Batch**. @all implies all the commands, both those currently present in the server, and those that will be loaded via modules in the future.

Keys

To allow and disallow certain keys and key permissions, click  **Add Key / Add Keys with Batch**. You can enable **Grant privilege of all keys** to allow the user to access all keys.


Channels


To allow and disallow Pub/Sub channels, click  **Add Channel / Add Channels with Batch**. You can enable **Grant privilege of all channels** to allow the user to access all Pub/Sub channels.

Privilege Manager

Besides setting privileges in each user, **Privilege Manager** provides another view on privileges in a connection and its database objects.

Note: Available only for MySQL, Oracle, PostgreSQL, SQL Server, MariaDB and MongoDB.

To add privileges, click  from the user object toolbar and follow the steps below:

1. Expand the node in the tree view until reaching to the target object.
2. Choose the object and click  to open the window.
3. Check the user on the left pane.
4. In the grid, check the relevant options against the privileges listed in **Privilege** to assign the selected user to have that object privilege.

Chapter 20 - Other Advanced Tools

Server Monitor (Available only in Navicat Premium, Enterprise and Standard Edition)

Navicat provides **Server Monitor** to view properties of selected servers. Choose **Tools** -> **Server Monitor** and choose the preferred server type from the menu bar.

Note: Available only for MySQL, Oracle, PostgreSQL, SQL Server, MariaDB and MongoDB.

Process List

This tab displays a list of processes from all selected servers. The process list provides detailed information. It depends on the database type you are chosen.

- CPU time and state of the process.

If you want to take action on auto-refreshing the process list in assigned seconds, choose **Server Monitor** -> **Set Auto Refresh Time** and enter a refresh time value. To enable or disable the Auto Refresh feature, choose **Server Monitor** -> **Auto Refresh**.

Note: Effect will take once you assign the value.

To set a selected process always show on the top of the grid, control-click and select **Set Always On Top** -> **Always On Top**. To cancel this setting, choose **Cancel** / **Cancel All**.

To stop a selected process, click the  button.

Variables

Note: Available only for MySQL, Oracle, PostgreSQL, MariaDB, MongoDB and Redis.

This tab displays a list of all server variables and their values.



You can edit MySQL, MariaDB, Oracle and Redis variable values here. Click  to open an editor for editing.

Status

Note: Available only for MySQL, Oracle, PostgreSQL, MariaDB, MongoDB and Redis.

This tab displays a list of all server status and their values.





Schema Analysis (Available only in Navicat Premium, Enterprise and Standard Edition)

Schema Analysis is used for verifying your schemas, visualizing data distributions and identifying data outliers. To start, select a collection or a view in the Objects tab and click , or click  in the data viewer.

Note: Available only for MongoDB.

Hint: Schema Analysis Profiles (.nsatmongodb) are stored under the [Settings Location](#).


Toolbar

Option / Button	Description
	Filter the documents for analyzing.
	Include or exclude fields for analyzing.
Analyze:	Select the sample documents from the collection for analyzing.
	Start analyzing the sample documents.
	Stop analyzing the sample documents.

Results

After the analysis has completed, you will see the schema analysis results. The results visually display information about the type and data distribution of all fields.

If a field has multiple field types, you can click the field type bar on the left, and the chart will show the data distribution chart of that type.








Command Monitor (Available only in Navicat Premium, Enterprise and Standard Edition)

Command Monitor is a real-time command monitoring tool that allows you to monitor every command processed by the Redis server instantly. It can help you understand what is happening to the database. To open the monitor, control-click on the connection and select **Command Monitor**.

Note: Available only for Redis.

Note: Command Monitor may reduce the performance of the Redis server significantly.

The toolbar provides the following functions:

Button	Description
	Start monitoring the Redis server.
	Stop monitoring the Redis server.
	Break long words and wrap onto the next line.
	Export the commands to a text file.
	Clear the commands.

Virtual Grouping

Virtual Group aims to provide a platform for logical grouping objects by categories, so that all objects are effectively preserved. It can be applied on Connection, Table, Collection, Data, View, Materialized View, Function, Index, Trigger, MapReduce, GridFS, Pub/Sub, Query, Aggregation Pipeline, Backup, Automation, Model and BI.

Hint: The vgroup.json file is saved under the default path, e.g. ~/Library/Application Support/PremiumSoft CyberTech/Navicat CC/Navicat Premium/Profiles

If you want to hide the group structure, choose **View -> Navigation Pane -> Flatten Connection** and choose **View -> Flatten Object List**.

Create a new group

1. In the main window, control-click on the Navigation pane or the Objects tab and select **New Group** or **Manage Group -> New Group**.
2. Enter a name for the new group.

Move an object to a group

1. In the main window, control-click an object and select **Manage Group -> Add to Group**.
2. Select an existing group.

Move an object to the top-level


1. In the main window, control-click an object and select **Manage Group -> Exclude From Group**.

Hint: You can also use the drag and drop method to move objects.

Connection Colorings

Navicat provides highlighting connections by colors for identifying connections and their database objects. It lets you immediately know which connection you're connected to when you working on database objects. The highlighted color displays in the Navigation pane and the tab of its object window.

To highlight a connection, control-click a connection in the Navigation pane and select **Color**.



Find in Database/Schema (Available only in Navicat Premium, Enterprise and Standard Edition)

Navicat provides a **Find in Database/Schema** feature offers searching table and view records or object structures within a database and/or schema. To open the Find in Database/Schema window, choose **Tools -> Find in Database/Schema** from the menu bar.

Note: Available only for MySQL, Oracle, PostgreSQL, SQLite, SQL Server, MariaDB and MongoDB.

1. Select a target **Connection, Database** and/or **Schema**.
2. Enter the search string in **Find**.
3. Choose to find Data or Structure in the **Look in** drop-down menu.
4. Choose the **Search Mode**: Contains, Whole Word, Prefix or Regular Expression.

5. Check the **Case Insensitive** box to disable case sensitive search if necessary.
6. When finding Structure, you can choose to search different objects: Tables, Collections, Views, Functions, Queries, Indexes, Triggers, Events and/or Materialized Views.
7. Click the **Find** button and then double-click an object in the **Find Results** list to view the record or the structure.

Console

Console allows you to use a command-line interface to work with your server. In other words, it provides interactive text-based screen for you to query input and result output from databases. To open the Console window, open a connection and choose **Tools** -> **Console** from the menu bar or press COMMAND-SHIFT-C.

Hint: You are allowed to open multiple console windows which each represents a different connection.

Oracle

For Oracle servers, you must have **SQL*Plus** executable for this feature to work. By default, Navicat will look for SQL*Plus under client folder (e.g. ORACLE_HOME\bin). However, if Navicat cannot locate SQL*Plus under the [SQL*Plus Executable Path](#), you are prompted to locate the executable.

Note: SQL*Plus does not support Unicode.

MongoDB


For MongoDB servers, you must have **Mongo Shell** executable for this feature to work. If Navicat cannot locate Mongo Shell under the [Mongo Shell default path](#), you are prompted to locate the executable.

Redis

For Redis servers, code completion and syntax highlighting are supported. It lets you type Redis commands smoothly.

Focus Mode (Available only in Navicat Premium, Enterprise and Standard Edition)


Focus is a feature that helps you reduce distractions and set boundaries. It removes everything from the screen except the form you are working and enters the full screen mode.

When you want to concentrate on a specific activity, you can turn it on by simply clicking the  icon.

The following tools support Focus Mode:

- Data Viewer
- Object Designer

- Query
- Aggregation Pipeline
- Automation
- Model
- BI
- Server Monitor

To exit Focus Mode, you can simply click the  icon at the top right.

Share via URI

Navicat allows you share an object with your teammates by the URI of the object. Navicat users can use the generated URI to access the object.

Here are the objects that can be shared:

- Connection
- Database / Schema
- Table / Collection / Data
- View / Materialized View
- Function / Procedure
- Query / Aggregation Pipeline
- Model
- BI

Obtain URI

You can obtain the URI of an object in the General tab of the Information pane. Simply click **Share** and copy the URI in the popup window. You can enable **Hide host info** to remove the connection host parameter in the URI.

Open Object via URI

1. In the main window, choose **File -> Open with Navicat URI**.
2. Paste the URI.
3. Click **OK**.

4. Change the connection mapping by clicking **Other Options** if necessary.

Option	Description
Mapped Connection	Automatically map the connection in the URI to the connection with the most similar information in Navicat.
Existing Connection	Choose an existing connection in Navicat.
New Connection	Create a new connection in Navicat.

5. Open the object.

Favorites (Available only in Navicat Premium, Enterprise and Standard Edition)

Favorites are links to objects that you visit frequently. By adding a path to your favorites list, you can go to that objects with a single click, instead of having to navigate the connection, database and/or schema in the Navigation pane.

Add a link to Favorites

1. Open an object, e.g. table.
2. Choose **Favorites** -> **Add to Favorites** or press OPTION-SHIFT-#.
3. Enter **Favorite Name** and select **Favorite ID**.

Open an object from Favorites

1. Choose **Favorites** -> **favorite_name** or press CONTROL-SHIFT-#.

Remove links from Favorites

- Choose **Favorites** -> **Clear Favorites** -> **favorite_name** to remove a link.
- Choose **Favorites** -> **Clear Favorites** -> **Clear All** to remove all links from the favorites list.

Note: # represents 1, 2, 3, 4, 5, 6, 7, 8 or 9.

Search Filter

Navicat provides search filters for searching your objects in the Navigation pane, the Objects tab, the Model Designer window and other tree structures.

Simply enter a search string in the **Search** text box directly. If connections have opened in the Navigation pane, the filter will also apply to their database objects.

You can remove the filter by deleting the search string.

Chapter 21 - Configurations

Settings

Navicat provides several options for customizing its user interface and performance.

To open the Settings window, choose **Navicat XXX -> Settings** from the menu bar.

General

Main Window

Show objects under schema

Display database objects using the tree structure in the Navigation pane. To expand a node, simply double-click it.

Hint: Reopen the database/schema to take effect.

Show objects under table

Display table elements (e.g. fields, indexes, foreign keys) using the tree structure in the Navigation pane. To expand a node, simply the arrow to the left of the table name.

Hint: Reopen the database/schema to take effect.

Font

Define the font and its size used by the object list.

Use default font

Check this option to use the default font settings.

Use safe confirm dialog

With this option is on, Navicat will prompt a double confirmation dialog for safe deletion when deleting objects in the main window.

Database items

Show function wizard

Display the function wizard (MySQL, Oracle, PostgreSQL, SQL Server or MariaDB) when you create a new function/procedure.

Query

Ask to save new queries/profiles before closing

With this option is on, Navicat will prompt you to save new queries or profiles every time when you quit the relevant sub-window.

Usage Data

Share Usage Data

Check this option to let your device sends us information about how you use Navicat to help us improve it. You can view the information being shared by clicking the **Usage Data** button.

Update

Automatically check for updates

Check this option to allow Navicat checks for new version when it starts.

Include anonymous system profile

Check this option to send us your system information, such as your macOS version to improve our Navicat when Navicat checks for updating.

Tabs

On Startup

Control what tabs appear when you launch Navicat:

Option	Description
Open Objects tab only	Open the Objects tab only, and no other tabs.
Continue where you left off	Open the Objects tab, and reopen the same tabs you were opened when you last quit Navicat.
Open a specific tab or set of tabs	Open the Objects tab, and open the tabs you choose in Set Tabs .

Open Tabs

Open new tab in

Set new pop-up windows to open as:

Option	Description
Main Window	Open a new tab in the main window.
Last Tab Window	Open a new tab in the last opened window (including the main window).
Last Tab Window (Except Main Window)	Open a new tab in the last opened window, or a new window if there isn't any opened windows.
New Window	Open a new window.

Allow opening multiple forms for same object

Check this option to allow opening multiple instances of an object.

Tab Bar Style

Always show the tab bar

Always show the tab bar when you open a window.

Code Completion

Use code completion

When you type the . (dot) symbol or a character, the editor will offer you a pop-up list that showing some suggestions for the code completion.

Auto update code completion info

With this option is on, Navicat will get the latest database information for code completion from your server automatically when you open the database/schema. Otherwise, you will need to update it manually in the Query window.

Include system objects when updating code completion info

When this option is on, code completion suggestions will also include system objects. In some cases, including system objects may slow down the code completion feature, especially in large databases.

Note: Only available for MySQL, MariaDB and PostgreSQL.

Auto select first suggestion

Select the first item automatically when the suggestion list pops up. Therefore, pressing ENTER or TAB will insert the selected item. Otherwise, you need to use arrow keys to select the suggestion item.

Clear Code Completion Info

Delete the information for code completion feature that stored on your device.

Editor

Disable syntax highlight and code completion if SQL larger than: MB

The highlighting and code completion features can be limited by setting the maximum file size (e.g. 10) to increase performance.

Show

Show line number

Display line numbers at the left side of the editor for easily reference.

Use code folding

Code folding allows codes to collapse as a block and only the first line displayed in the editor.

Use brace highlighting

Highlight the pair of braces when your cursor moves to either one brace for easily reference.

Use syntax highlighting

Syntax highlight helps viewing codes clearly. Codes are highlighted in the editor with different colors and fonts according to the categories they belong to.

Text Layout

Tab Width: spaces

Enter the number of characters that a tab occupies, e.g. 5.

Insert spaces when pressing Tab

Insert space characters when the Tab key is pressed.

Use word wrap

Enable the word wrap mode in the editor.

Font and Colors

Font

Define the font and its size used by the editor.

Use default font

Check this option to use the default font settings.

Syntax Colors

Format your queries in the editor with colored syntax highlighting to improve readability. Set font colors to mark out different text fragments: Common, Keyword, String, Number, Comment and Background. Click on the color boxes and choose your desired color from the Colors dialog window.

Records


Records



Limit records records per page

Check this option if you want to limit the number of records showed on each page in the grid globally. Otherwise, all records will be displayed in one single page.

Note: To adjust the settings for particular table/collection, see [Data Viewer](#).

Auto begin transaction

Check this option to start a new transaction automatically when changing records in the table/collection. Otherwise, auto commit is on and you need click the  button in Data Viewer to start a transaction manually.


When starting a transaction in Data Viewer, you can use the  or  button to commit or rollback the changes. See [Data Viewer](#).

Synchronize record after modifying

When updating/inserting a row in the grid (if primary key exists), it will reload this record from the server.

For example: a table with 3 columns - id, name and timestamp. If you update the name column, the timestamp will update immediately in the grid.

Enable batch update mode

With this option is on, data changes will not be posted to the server when selecting another row, until clicking the  button.

Grid

Font

Define the font and its size used by the grid.

Use default font

Check this option to use the default font settings.

Row shading

Apply shading to alternate rows or every third row in the grid for viewing data clearly. Choose **None** if you do not want to apply shading.

Auto Recovery

Autosave modified queries

Save automatically after modifications in queries by defining the interval (e.g. Every 30 seconds).

Autosave modified models

Save automatically after modifications in model workspaces by defining the interval (e.g. Every 3 minutes).

Autosave modified BI workspaces

Save automatically after modifications in BI workspaces by defining the interval (e.g. Every 3 minutes).

Environment

Executables

SQL*Plus Executable Path (Available only for Oracle)

Specify the location of SQL*Plus used in the [console](#) of Oracle connections. SQL*Plus is included in Oracle Instant Client.

SQLite3 Dynamic Library Path

Specify the location of SQLite3 Dynamic Library.

Hint: Restart Navicat to take effect.

Mongo Shell Path (Available only for MongoDB)

Specify the location of Mongo Shell used in the [console](#) of MongoDB connections.

MongoDump Executable Path (Available only for MongoDB)

Specify the location of the mongodump executable that used for [MongoDump](#).

MongoRestore Executable Path (Available only for MongoDB)

Specify the location of the mongorestore executable that used for [MongoRestore](#).

MongoImport Executable Path (Available only for MongoDB)

Specify the location of the mongoimport executable that used for [MongoImport](#).

MongoExport Executable Path (Available only for MongoDB)

Specify the location of the mongoexport executable that used for [MongoExport](#).

External Editor

Choose the file path of an external editor for opening queries.

OCI Environment (Available only for Oracle)

Hint: Restart Navicat to take effect.

OCI library (libclntsh.dylib)

Specify the location which contains Oracle libraries for instant client and SQL*Plus (e.g. ORACLE_HOME/lib). Always required.

Use bundled OCI library

Oracle library has already included in Navicat. Check this option to use the bundled library, e.g. /Applications/Navicat Premium.app/Contents/OCI.

Oracle Instant Client is the simplest way to deploy a full Oracle Client application built with OCI, OCCI, JDBC-OCI, or ODBC drivers. It provides the necessary Oracle Client libraries in a small set of files. You can also download Oracle Instant Client through -

[Oracle Instant Client](#)

Download the appropriate Instant Client packages for your platform and the CPU. All installations REQUIRE the Basic or Basic Lite package. Unzip the packages and set the path points to it.

ORACLE_HOME

Specify the location of ORACLE_HOME for full client only. Instant client should leave it blank.

TNS_ADMIN

Specify the location of the tnsnames.ora file (e.g. ORACLE_HOME/network/admin). It is optional. Required when using TNS connection.

Advanced

Logs Location

Logs Location

Specify the location for storing the log files.

Enable diagnostic logging

Generate a log file to assist with tracking down any problems in Navicat.

Hint: Restart Navicat to take effect.

Connectivity

Verify server certificate against CA

Enable this option to verify that the server certificate against the list of trusted CA.

Connectivity Diagnosis

Click **Test Connectivity** to test the network connectivity between the web service and your machine.

Chapter 22 - Hot Keys

Navicat Hot Keys

Common

Keys	Action
COMMAND-R	Refresh
COMMAND-N	New Object
COMMAND-D	Design Object
SHIFT-COMMAND-D	Duplicate Object
OPTION-SHIFT-# (# represents 1 to 9)	Add to Favorites
CONTROL-SHIFT-# (# represents 1 to 9)	Open Favorites Link
COMMAND-} or COMMAND-{	Select Next / Previous Tab
COMMAND-> or COMMAND-<	Select Next / Previous Page
COMMAND-Y	New Query
COMMAND-U	Open with Navicat URI
COMMAND-S	Save
SHIFT-COMMAND-S	Save As
COMMAND-W	Close Tab
SHIFT-COMMAND-W	Close Window

Navicat Main Window

Keys	Action
COMMAND-1	Show / Hide Navigation Pane
COMMAND-2	Show / Hide Information Pane
OPTION-COMMAND-T	Show / Hide Toolbar
CONTROL-COMMAND-F	Full Screen
SHIFT-COMMAND-C	Console
SHIFT-COMMAND-H	History Log
SHIFT-COMMAND-.	Close Connection / Database / Schema
SHIFT-COMMAND-T	Data Transfer
SHIFT-COMMAND-F	Find in Database/Schema

ER Diagram View

Keys	Action
ESC	Select
H	Move Diagram
R	New Foreign Key
DELETE	Delete Selected Foreign Key
COMMAND-Mousewheel Up	Zoom In

COMMAND-Mousewheel Down	Zoom Out
COMMAND-0	Reset Zoom

Table / Collection Designer

Keys	Action
COMMAND-0	Open Table / Collection
COMMAND-+	Add Field
COMMAND-D	Duplicate Field
COMMAND--	Delete Field
SHIFT-COMMAND-K	Set Field as Primary Key
COMMAND-UP ARROW	Move Up
COMMAND-DOWN ARROW	Move Down
COMMAND-F	Find Field
COMMAND-G	Find Next Field
SHIFT-COMMAND-G	Find Previous Field

Data Viewer

Keys	Action
COMMAND-D	Design Object (Table, Collection, View, Materialized View)
SHIFT-COMMAND-Y	Query Object (Table, Collection)
COMMAND-F	Find Text
COMMAND-G	Find Next Text
SHIFT-COMMAND-G	Find Previous Text
OPTION-COMMAND-F	Find and Replace
COMMAND-UP ARROW	Sort Ascending
COMMAND-DOWN ARROW	Sort Descending
CONTROL-OPTION-COMMAND-F	Filter Wizard
COMMAND-+	Add Record
COMMAND--	Delete Records
COMMAND-RETURN	Apply Record Changes
COMMAND-ESC	Discard Record Changes
COMMAND-.	Stop Loading Data
CONTROL-0	Set to NULL
CONTROL-SHIFT-B	Toggle Image Editor
CONTROL-SHIFT-T	Toggle Text Editor
CONTROL-SHIFT-H	Toggle Hex Editor
CONTROL-SHIFT-W	Toggle Web Editor
SHIFT-COMMAND-V	Switch View

View / Materialized View Designer

Keys	Action
COMMAND-R	Preview
COMMAND-.	Stop

Query Designer

Keys	Action
COMMAND-R	Run / Run Selected
SHIFT-COMMAND-R	Run Current Statement
COMMAND-.	Stop

Query Editor

Keys	Action
COMMAND-F	Find Text
COMMAND-G	Find Next Text
SHIFT-COMMAND-G	Find Previous Text
OPTION-COMMAND-F	Find and Replace
COMMAND-UP ARROW	Go to the Beginning of Page
COMMAND-DOWN ARROW	Go to the End of Page
COMMAND-LEFT ARROW	Go to the Beginning of Current Line
COMMAND-RIGHT ARROW	Go to the End of Current Line
COMMAND-]	Increase Indent
COMMAND-[Decrease Indent
COMMAND-/	Toggle Comment
COMMAND-+	Zoom In
COMMAND--	Zoom Out
COMMAND-0	Reset Zoom

Debugger

Keys	Action
F9	Run
F10	Step Over
F11	Step In
COMMAND-F11	Step Out

Model

Keys	Action
Diagram	
COMMAND-P	Print
ESC	Select
H	Move Diagram
T	New Table/Collection/Entity

V	New View
R	New Foreign Key/Relation
A	New Label
N	New Note
I	New Image
L	New Layer
COMMAND-Mousewheel Up	Zoom In
COMMAND-Mousewheel Down	Zoom Out
COMMAND-0	Reset Zoom

BI

Keys	Action
COMMAND-D	Design Object
COMMAND-R	Refresh Data
OPTION-COMMAND-P	Present Dashboard


Chapter 23 - Trace Logs

Log Files


Navicat provides number of log files to keep track on the actions have been performed in Navicat and they are located in the default folder, e.g. ~/Library/Application Support/PremiumSoft CyberTech/Navicat CC/Navicat Premium/Logs. You are allowed to change the log files location under [Settings](#).

File	Description
QueryExec.log	Store the statements or scripts of all operations executed over databases and database objects in Navicat. To open the QueryExec.log file in the History Log Viewer , choose Tools -> History Log or press SHIFT-COMMAND-H. Note: This log will be overwritten while Navicat is being restarted.
cmdline.log	Store information for Navicat command line process and all operations while running batch jobs.
LogImport.txt	Record detailed information on every error (indicating success or failure) that occurred during the import process. Note: This log will be overwritten on each import.
navicat.log	Store information to assist with tracking down any problems in Navicat. You can enable this log in Settings . Note: This log will be overwritten while Navicat is being restarted.

History Log Viewer

History Log Viewer shows the statements or scripts that are executed or executing in Navicat. If you just want to display error messages, click . You can also change the information shown by choosing from the **View** menu -

- Show Date
- Show Time
- Show Server Name
- Show Session ID
- Show Connection Type
- Show Execute Time

Note: When you click , any actions that you do while history is paused will show after resuming.